25 Setting Recipes

This chapter explains how to use recipes in GP-Pro EX and the basic functions used for Recipes.

Please start by reading "25.1 Recipes" (page 25-2) and then turn to the corresponding page.

25.1	Recipes	
25.2	Settings Menu	
25.3	Creating CSV Data Recipes	25-10
25.4	Transferring CSV Data Recipes Using Touch	25-18
25.5	Transferring CSV Data Recipes from the Device	
25.6	Displaying/Editing CSV data on the Screen	25-29
25.7	Creating Filing Data Recipes	25-41
25.8	Transferring Recipes (Filing Data) (Using Manual Transfer)	
25.9	Transferring Recipes (Filing Data) Using Automatic Transfer	
25.10	Settings Guide	
25.11	How to Transfer CSV Data	
25.12	Mechanism of Filing Data Transfer	25-105
25.13	Restrictions	25-113

25.1 Recipes

25.1.1 What are Recipes?

This feature is used to create recipes with preset data to write to the device/PLC. You can rewrite large numbers of data in the device/PLC by transferring the Recipe data. These recipes can be used in process and production control to specify settings for machine operation (material quantities, heat settings, etc.)



Also, you can read device/PLC data and register it as a new recipe.



25.1.2 Types of Recipes

There are two types of Recipes:

Transfer CSV Data

Data for which a recipe is created using common spreadsheet software (such as Microsoft Excel) and is converted to a CSV file, or recipe data created in CSV format from the beginning on GP-Pro Ex is referred to as "CSV Data".

Write the CSV data saved on the CF Card or USB storage device to the device/PLC, read the device/PLC data, and then save the data on the CF Card or USB storage device as a CSV file.

• The [CSV Data Transfer Function] is suitable for creating standardized data and dividing files into recipes.

Transfer Filing Data

Recipe data (binary data) created in GP-Pro EX is called "Filing Data".

These recipes write data from the backup SRAM to the device/PLC, and stores data from the device/PLC to backup SRAM.

Recipe Data	Attribute
CSV Data	 Transfer the data directly between a CF Card or USB storage device and the device/PLC. Display on the display unit screen to edit and print the data on the CF Card or USB storage device. Can be created and edited in spreadsheet software (e.g., Microsoft Excel). One recipe must be handled as one CSV file.
Filing Data	 Keep the recipe in the display unit as internal data without using a CF Card or USB storage device. You cannot display or edit data on the display unit screen. By transferring data via the display unit internal device, you can display and edit data on the screen. Multiple recipes, transferred to the same address, can be handled as a single file.

Attributes of CSV data and filing data

CSV Data Flow

You can transfer CSV data from the CF Card or USB storage device and the device/PLC.



There are two methods for transferring CSV data: control the transfer from the device/PLC (Automatic Transfer), or control the transfer by touching the GP screen (Manual Transfer).

Transfer Methods

Automatic transfer	Set the control address. Each time the bit is turned ON by the device, the data is transferred. The transfer action can be set as Condition Action or Address Action.			
	Condition Action	 Transfer according to a previously set condition. NOTE By using the Condition Name Search feature, only data that corresponds with the designated condition name is transferred. 		
	Address Action	The address is set at the time of transfer. The destination address for each file to be transferred can be changed.		
Manual transfer	Place a Special Data Display [Data Transmission] on the screen, select the file to transfer, and touch the transfer switch. Data is then transferred.			

Filing Data Flow

Filing data created in GP-Pro EX is transferred to the display unit's internal memory or the CF Card by screen transfer. In order to transfer data to the PLC, you need to first write data to backup SRAM. This is called "Transfer Preparation".

After transfer preparation, filing data is transferred between backup SRAM and the device/PLC.



- *1 Memory where the screen data is stored. Filing data is stored in memory via a screen transfer.
- *2 Transfer Project cannot transfer the data in USB Storage Destination Folder to the USB storage device inserted in the display unit. Copy the data in the folder to the USB storage device manually, and store the USB storage device on the display unit.

IMPORTANT	Filing data in backup SRAM cannot be edited on the display unit. It can only be edited in GP-Pro EX.
	To edit data on the display unit, transfer it via the display unit's internal device, and use Data Display to edit the data stored in the internal device.

There are two methods for transferring Filing data: control the transfer from the device/PLC (Automatic Transfer), or control the transfer by touching the GP screen (Manual Transfer).

Transfer Methods

Automatic transfer	Set the control address and transfers data when the PLC trigger bit turns ON.
Manual transfer	Place a Special Data Display [Filing] on the screen, select the data (block) to transfer, and touch the transfer switch. Data then transfers.

25.2 Settings Menu







(Creating Filing Data Recipes					
С	reating a recip	e in GP-Pro				
(Filing	g Data			
		Block 0	Block 1	Block 2		
	Item Name	Bread	Butter Roll	Croissant		
	[PLC1]D00100	350	400	200		
	[PLC1]D00101	5	8	4		
	[PLC1]D00102	7	8	3		
	[PLC1]D00103	12	16	10	Setup Procedure (page 25-42)	
	[PLC1]D00104	245	310	120	Introduction (page 25-41)	
	[PLC1]D00105	12	40	10		





25.3 Creating CSV Data Recipes

25.3.1 Introduction

Create a CSV Data Recipe to write to the CF Card of the device.

There are two methods for creating Recipes: creating a spreadsheet and saving it as a CSV file or creating a recipe in GP-Pro EX.



25.3.2 Setup Procedure

■ Creating CSV Data Recipes with Excel

To create a recipe using a spreadsheet, first create the spreadsheet in Microsoft Excel, save it as a CSV file, and then save it to a CF Card or USB storage device.



1 Open Microsoft Excel and enter items of ":DATE", ":Group NO.",":GROUP NAME", "ITEM NAME", and "VALUE" to the appropriate locations and enter the recipe data. The GP transfers the data according to these parameters:

🔛 Mi	crosoft Excel - B	ook1						
<u> 1</u>	🕙 <u>Fi</u> le <u>E</u> dit <u>V</u> iew Insert Format <u>T</u> ools <u>D</u> ata <u>W</u> indow <u>F</u>							
	🖻 🔒 🔒 😂	Q	🂱 👗 🛍 🛍	🗠 + 🍓				
	F8 💌		=					
	А		В					
1	: DATE		2005/4/30 1	0:30:00				
2	: GROUP NO	D.		0 —	Date/Time			
3	: GROUP NA	ME	Butter Role	-	Condition Number			
4	ITEM NAME		VALUE		Condition Name			
5	Flour			400	Condition ratio			
6	Yeast			8				
7	Salt			8				
8	Sugar			16	—— Data area			
9	Milk	\backslash		310				
10	Butter			40				
11								

Enter Data Item Names or Transfer Address as needed (These entries will not be transferred to the Device)

:DATE

Enter the data creation date.

:GROUP NUMBER

Enter the Condition Number to transfer.

:GROUP NAME

Enter an optional Condition Name.

ITEM NAME

You can use the area below the ITEM NAME field to enter comments or additional information as necessary.

VALUE

You can use the area below the ITEM NAME to enter any other information.

NOTE	• Only the data portion will be transferred to the device via Transfer CSV Data. Enter the Condition Number, the Condition Name, and comment as required. When transferring data, regardless of Condition Number and Condition Name, they are transferred according to the conditions set in the [Transfer CSV Data
	(Condition) (T)]. You can access these from the [Recipe (R)] under [Common Settings (R)].

2 Save the file to the CF Card or the USB storage device. Specify the destination to save the file in the CF Card or USB storage [FILE] folder. Select "CSV" for the file. Set the file name to "ZR*****.csv", where ***** is a 5-digit file number from 00000 to 65535.

Microsoft Excel - ZR00001							
₽] <u>E</u>							
0	🗲 🔒 🔒 🔒 😫	> 🖌 🖻 🛍 🗠 -					
	F8 💌	=					
	A	В					
1	: DATE	2005/4/30 10:30:00					
2	: GROUP NO.	0					
3	: GROUP NAME	Butter Role					
4	ITEM NAME	VALUE					
5	Flour	400					
6	Yeast	8					
- 7 -	Salt	8					
8	Sugar	16					
9	Milk	310					
10	Butter	40					
4.4							

The Recipe is created.

If your computer does not have CF Card drivers, set the CF Card export folder and save. The CF Card output folder data is transferred to the GP's CF Card via a screen transfer.

• To select the CF Card Folder in GP-Pro EX, from the [Project (F)] menu, point to [Information (I)] and select [Destination Folder (C)]. [©] "5.7.2 Setup Procedure ■ Setting the Destination Folder" (page 5-53)

Editing Data in Microsoft Excel

You can edit and save data transferred from the device/PLC to the CF Card or USB storage device in Microsoft Excel. When opening the CSV file in Microsoft Excel, the following appears:

🕺 ZR00001.csv					
	A	В			
1	:DATE	30/04/2005 10:30:00			
2	:GROUP NO.	1			
3	:GROUP NAME	Butter Rolli			
4	ITEM NAME	VALUE			
5		400			
6		8			
7		8			
8		16			
9		310			
10		40			

:DATE

Records the date when the file was saved to the CF Card or USB storage device. The date is recorded using a 4-digit year. For example:

:GROUP NUMBER

The Condition Number set in the conditional settings is written.

:GROUP NAME

The Condition Name set in the conditional settings is written.

ITEM NAME

The area below this item is blank.

VALUE

The area below this item contains the transferred data.

■ Creating Recipe Data in GP-Pro EX

```
NOTE
```

• Please refer to the Settings Guide for details.

"25.10.1 Common (Recipe) Setup Guide ■ Transferring CSV Data (CSV File List)" (page 25-59)

Create a recipe in GP-Pro EX then save to a CF Card or USB storage device.



The following procedure explains how to save CSV data on a CF Card or USB storage device.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [CSV Data Transmission (CSV File List) (F)]. In [Save In] select [CF Card] or [USB Storage].

📃 Base 1 (Untitled) 🗵 📆 CSV	File 🗵		4 Þ
Recipe Settings (Transfer CSV Data)	<u>Go to Conditio</u>	in Settings	
	USB Storage <u>VPro-face\GP-ProEX 2.1</u> C File Name A	<mark>9\\file</mark> xdd Update	
File Name ondition Numb	Condition Name	Data Items	

If the CF Card Folder is not yet set, the following message appears. Click [Yes (Y)].



Select the [Enable CF Card] check box. Click [Browse] and set the CF Card Folder. Click [OK (O)].

💰 Project Informa	tion	Х
File Information Display Unit Send Data SRAM Information Destination Passwords Logic Memory	CF-Card Destination Folder	
	USB Storage Folder USB Storage USB Storage Destination Folder Browse	
	OK (<u>D</u>) Cancel	

- The CF Card Folder is the location where created data is temporarily saved inside the project. The data saved here is saved to the CF Card via a screen transfer.
 - The CF Card Folder can be set using this method or set from the Project Properties.
 - Specify the USB Storage Destination Folder when you select [Save in] and point to [USB storage]. You cannot use project transfer to move the saved data saved to the display unit's USB storage device. You must manually copy the data to the USB storage device and then connect the device to the display unit.
- 2 Click [Add]. The [Add CSV File] dialog box appears. Set the [CSV File Number] and click [OK (O)].

In the file name "ZR*****.csv", **** represents the file number portion set here.

	💰 Add CSV File	×
Add Update	CSV File Number	∃∎
	OK (<u>O</u>) Cance	

• To enable [Add], [Transfer CSV Data] should be selected in the [Recipe (R)], [Transfer CSV Data (Condition) (T)] tab. **3** The [Edit CSV File] dialog box appears.

In [Condition Name (Group Name)], enter the recipe name. Enter each value and title, then click [OK (O)].

	umber (Group Number) ame (Group Name)	0 🕂 🧾 Bread		Number 6	of Data
	Title		Valu	le	
1	Flour				400
2	Yeast				8
3	Salt				8
4	Sugar				16
5	Milk				310
6	Butter				40

4 The recipe appears in the file list.

📮 Base 1 (Untitled) 🗵 📆	CSV File 🗵 📆 CSV Condition 🗵		4 ⊳
Recipe Settings (Transfer CSV D	Pata) <u>Go to Condition Settings</u>		<u> </u>
File Name Condition	Number Condition Name	Data Items	
ZR00000.csv 0	Bread	6	

When you wish to edit the data, display the [Edit CSV File] dialog box according to the following method and edit it.

- Double-click the cell in the file that you wish to edit.
- Right-click the cell in the file that you wish to edit, and click [Edit] from the displayed menu.
- Select the cell in the file that you wish to edit and press the [Ctrl] + [E] keys.

The recipe is saved in the [FILE] folder in the designated CF Card output folder with the created recipe (ZR00000.csv).

	1st Column	2nd Column	
1st Row :	DATE	(Date Saved)	
2th Row :	GROUP NO	(Condition No.)	
3rd Row	GROUP NAME	(Condition Name)	
4th Row I'	TEM NAME	VALUE	
5th Row F	Flour	350	
6th Row	Yeast	5	
7th Row S	Salt	7	Created data
8th Row S	Sugar	12	
9th Line N	Milk	245	
10th Row E	Butter	12	

- ":DATE", ":GROUP NO", ":GROUP NAME", ":ITEM NAME" and "VALUE" are fixed.
- Dates are written in the format "yyyy/mm/dd hh:mm:ss".
- The Condition Number and Condition Name are written.
- Below "ITEM NAME" in the first column, the designated titles are written.
- Below "VALUE" in the second column, the designated values are written.

25.4 Transferring CSV Data Recipes Using Touch

25.4.1 Introduction

The recipe (CSV data) saved on the CF Card or USB storage device displays in a list on the display unit.



Touch to select or clear the recipes you want to send to the device/PLC.



NOTE

- Device/PLC data overwrites the selected files on the CF Card or USB storage device. You cannot save data as a new file when you manually transfer from the device/PLC to the CF Card or USB storage device.
- To overwrite Device/PLC data in an existing CSV file, you can select [All Files] or [Overwrite Data Only]. The [Overwrite Data Only] option overwrites dates and values only and leaves other data unchanged.

25.4.2 Setup Procedure

NOTE	Please refer to the Settings Guide for details.
	^C "25.10.1 Common (Recipe) Setup Guide ■ Transfer CSV Data (Condition)" (page 25-54)
	^{C∰} "25.10.2 [Special Data Display] Settings Guide ■ Data Transmission" (page 25- 70)
	 For details of the part placement method and the address, shape, color, and label setting method, refer to the "Part Editing Procedure". ** "8.6.1 Editing Parts" (page 8-44)

On the GP screen's Special Data Display [Data Transmission], set the options for transferring CSV data by touch.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer CSV Data (Condition) (T)] command, or click represented from the toolbar. The following window appears.

📮 Base 1 (Untitled) 🛛 📉 CSV Con	dition 🗵	${\bf A} \triangleright {\bf X}$
Recipe Settings (Transfer CSV Data)	Go to CSV File List	
🔲 Transfer CSV Data		
Action Mode Condition Action	Z Write Mode 🛛 All Files 💌 Language 🛛 ASCII 💌	
Control Word Address	🗖 Condition Name Search Feature	
	Search Word Address	

- 2 Select the [Transfer CSV Data] check box, and define the [Action Mode] as [Condition Action], and [Write Mode] as [All Files].
- **3** In [Condition], click [New]. The [CSV Data Transfer Condition] dialog box appears.

💰 CSV Data Transfer C	ondition 🛛 🗙
Condition Extended	
Condition Number (Group Number)	0 🗮 🏢
Condition Name (Group Name)	
Destination	
Destination Word Address	[PLC1]D00000
Number of Data	1 🗄 🏢
Data Type	Dec 💌 🗆 Sign +/-
Bit Length	16 Bit 💌
File Number	
Start	0 🗦 🏢
End	65535 🛨 🏢
	OK (0) Cancel

4 Enter the [Condition Number] and [Condition Name] to be registered. (Example: Condition Number: 0, Condition Name: Materials)

- **5** In the [Destination Word Address] field, set the start address for the destination device/PLC address (D100) and then set the number of data items (6), data type (Dec), and bit length (16 bit) to transfer.
- 6 Designate the [Start] and [End] of the recipe file (ZR****.csv).



7 Click [OK (O)].

The condition appears in the [Condition] list.

E Base 1 (Untitled) 🛛 📆 CSV Condition 🗵	4 Þ
Recipe Settings (Transfer CSV Data) Go to CSV	<u>V File List</u>
✓ Transfer CSV Data	
Action Mode Condition Action 💌 Write Mo	1ode 🛛 All Files 💌 Language 🖉 ASCII
Control Word Address	Condition Name Search Feature
	Search Word Address
Condition <u>New</u>	
ondition Numb Condition Nam Address Data Item	ems File Number
0 Material [PLC1]D00100 6	0-10

Create as many conditions as required.

• Select and enter the [Delete] key from the list, and the registered recipe (CSV Data) will be deleted.

8 Open the screen editor. From the [Parts (P)] menu, point to [Special Data Display (P)] and select [Data Transmission (D)] or click 📰 from the toolbar. Place the Part on the screen.

		_															 _		_				
		יייס		• •	• 1		1		 ' 2	1	• •	1			3		۰.			1		4 '	1.1
-	_																						
-			_																				
-																							
0																							
		· ·																					
1-1				12	2.4.1	5.6.		 	 				 	7 2	9 0	1	 4.5	6	7 2	9		_	<u> </u>
11				50											22						Κ.	_	
				3 -					 								 				Ç,		>/
		, i		4 -																			_
1				5 -													 				\vee		
1-1				6 -																	-	×	E.
		1		7 -																	\geq		
				8 -																			
1.1				9 -																	1	UE) ¹
1-1				10																	N		/
				11																	H	=	-
				12																	K,		
2																					ĸ	UΜ	9
1.1																						-	4
-																					V		
11																					,D	ΞS	P,
11																							<u>/</u>

9 Double-click the new Special Data Display. The settings dialog box appears.

<i></i> Special Data Display		×
Parts ID SP_0000 == Comment	Basic Display Color Switch Display Unit Data Transmission Filing Show CSV File Manager	
	Transfer Status	
Help (H)	OK (Q) Canc	el

10 Select the [Display] tab. Set the [Font] and [Display Format].

Basic Display Color S	Switch		
Font			
Font Type Standar	rd Font 💌	Size 8 x 8 Pixels	-
Display Format			
Border 💿	0	° 🔲	
No Border	Show Border	Border with Horizontal Lines	
Display Characters	40 🗄 🏢		
Display Rows	12 📑 🏢		

11 Select the [Color] tab. Set the text and background color.

Basic Display Color	Switch		
Display Color	7	Blink	None
Background Color		Blink	None
Clear Color	0	Blink	None

12 Select the [Switch] tab and select the operation switches you want to place. Set the number of rows that a scroll switch moves when pressed. Select the shapes, label and text color, and click [OK (O)].

Parts ID SP_0000 im Comment SP_000 Select Shape	Basic Display Color Switch Switch Layout Transfer from CF/USB to Device/PLC Transfer from Device/PLC to CF/USB Scroll Up Samples to Scroll Scroll Down Samples to Scroll Switch Label Font Type Standard Font Select Switch Display Switch Color Transfer from CF/USB to Device/PL CF-> Switch Color Switch Color Switch Color Z< Blink None Pattern None None Suitel Suitel Suitel Switel Suitel Switel Switel Switel Suitel Switel Switel Suitel Switel Suitel Suitel	
Нер (Н)	OK (Q) Cancel	
• Depending	g on the switch type, [Switch Color] may be enabled	•

• When you select a switch and press the [F2] key you can directly edit the text on the label.

The Special Data Display Part [Data Transmission] is now configured. You can move the switches to the appropriate locations.



NOTE

 If you want to display CSV data on the GP screen, place a Special Data Display [Show CSV].
 "25.6 Displaying/Editing CSV data on the Screen" (page 25-29)

25.4.3 Transfer Process

Display the file number (***** in ZR****.csv) from the CF Card or USB storage device and the condition name on the display unit using a Special Data Display [Data Transmission].

1 Select the file to transfer by touching it. You can select multiple files from the displayed list. If you touch a scroll switch while a file is selected, the displayed page changes and the selection cancels.



2 Touch the CF Card/USB to Device/PLC or Device/PLC to CF Card/USB transfer switch. Each file number is transferred according to a previously set condition.



- When transferring data from the device/PLCCF/USB, if Write Mode is set to [All Files], all data on the CF Card or USB Storage will be overwritten. In such cases, the Condition Name of the file is overwritten with the Condition Name defined in the Condition settings.
 - If you have selected multiple files, the transfer occurs in order starting with the smallest file number.
 - In the Special Data Display [Data Transmission], CSV files appear in the order they were created. It is not possible to sort the files by file numbers or time stamps.

If both a Special Data Display [Data Transmission] and [Show CSV] are placed on the same screen and you select a file and press the display switch, CSV Data Recipes appear in the [Show CSV].



NOTE	• If you select multiple files and touch the display switch, the file with the smallest file number displays.
	 If you set up the Special Data Display [Show CSV] to allow editing of data, you can edit the displayed data by touch. Use this feature when you want to edit CSV data in a CF Card or USB storage on the screen and write to the device/PLC. You can use a Special Data Display [File Manager] and display/edit it in a [Show CSV].

"25.6 Displaying/Editing CSV data on the Screen" (page 25-29)

25.5 Transferring CSV Data Recipes from the Device

25.5.1 Introduction

When bit 0 of the specified control address is ON, the specified CSV data in the CF Card or USB storage device is written to the device/PLC following the preset transfer conditions (such as transfer designation address, number of data).



Also, when bit 1 of the Control Address turns ON, the device/PLC data is read and saved to the CF Card or USB storage device as new CSV data according to the previously set transfer conditions (Destination Address, Number of Data Items)



NOTE

• You can transfer multiple files up to a maximum of 64 at one time.

- You can designate the destination or source address, Number of Data Items, etc., for each file at transfer time.
 - [™] "25.11.2 Control Word Address ◆ For Address Action" (page 25-92)

25.5.2 Setup Procedure

```
NOTE
```

Please refer to the Settings Guide for details.
 ^{CP} "25.10.1 Common (Recipe) Setup Guide ■ Transfer CSV Data (Condition)" (page 25-54)

Configure settings so that when the designated address bit 0 turns ON, the specified CSV data is transferred according to the set condition.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer CSV Data (Condition) (T)] command, or click 🔯 from the toolbar. The following window appears.

📮 Base 1(Untitled) 🛛 🔁 CSV Condition 🖂	${\bf A} \triangleright {\bf X}$
Recipe Settings (Transfer CSV Data) <u>Go to CSV File List</u>	
Transfer CSV Data	
Action Mode Condition Action 💌 Write Mode All Files 💌 Language ASCII 💌	
Control Word Address Condition Name Gearch Feature	
Search Word Address 🛛 🔽 🔤	

- 2 Select the [Transfer CSV Data] check box, and define the [Action Mode] as [Condition Action], and [Write Mode] as [All Files].
- **3** Select the [Control Word Address] check box and set the address (D50) used to operate the transfer from the device/PLC.

• Four consecutive words that include the specified address are used.

4 In [Condition], click [New]. The [CSV Data Transfer Condition] dialog box appears.

💰 CS¥ Data Transfer C	ondition	×
Condition Extended		
Condition Number (Group Number)	0 🗄 🏢	
Condition Name (Group Name)		
Destination		
Destination Word Address	[PLC1]D00000	
Number of Data	1 🗄 🏢	
Data Type	Dec 💌 🗖 Sign +/-	
Bit Length	16 Bit 💌	
File Number		51
Start	0 📑 🧮	
End	65535 🛨 🏢	
	OK (0) Cancel	

- 5 Enter the [Condition Number] and [Condition Name] to be registered.
- 6 In the [Destination Word Address] field, set the start address for the destination device/PLC address (D100) and then set the [Number of Data Items], [Data Type], and [Bit Length].

7 Designate the [Start] and [End] of the recipe file (ZR****.csv).

-File Number- Start End		Files "ZR00000.csv" to — "ZR00010.csv" are transferred
End	10 🖃 🏢	according to the condition.

8 Click [OK (O)].

The condition appears in the [Condition] list.

📮 Base 1(Untitled) 🛛 🔁 CSV Condition 🖂	⊲ ⊳
Recipe Settings (Transfer CSV Data) <u>Go to CSV File List</u>	
☑ Transfer CSV Data	
Action Mode Condition Action 💌 Write Mode 🛛 All Files 💌 Language ASCII	•
Control Word Address	
[PLC1]D00050 🗾 📄 👔 Search Word Address 🔄 🖃	
Condition <u>New</u>	
ondition Numb Condition Nam Address Data Items File Number	
0 Material [PLC1]D00100 6 0-10	

Create as many conditions as required.

NOTE

• If you set the [Condition Name Search Feature] and enter a condition name to search for, the CSV files with that condition name are found and transferred.

^(C) "25.11.3 About the Condition Name Search Feature" (page 25-97)

• When using automatic transfer from device/PLCCF/USB, you can automatically assign the file numbers and create new CSV files or USB storage.

^(C) "25.11.4 About Automatic Numbering" (page 25-103)

• To overwrite Device/PLC data in an existing CSV file, you can select [All Files] or [Overwrite Data Only]. The [Overwrite Data Only] option overwrites dates and values only and leaves other data unchanged.

25.5.3 Transfer Process

Transfer CF/USB to Device/PLC

Transfer a single recipe file "ZR00000.csv" to a device/PLC.

D50	Control	
D51	Status	
D52	Number of Files	<"1"
D53	File Number 1	<"0"

- 1 In D52, store the number of CSV files to transfer "1".
- 2 In D53, store the File Number "0".
- **3** Turn ON D50 bit 0. According to the settings of Condition Number 0, data transfers into 6 words, D100 to D105.

During the data transfer, D51 (Status address) bit 0 (Transferring Bit) turns ON.

4 When all files have completed transfer normally, D51 bit 0 turns OFF, and bit 1 (Transfer Complete Flag) turns ON. Turn OFF D50 bit 0.

Transfer Device/PLCCF/USB

Save 6 words of data, D100 to D105, to the CF Card as "ZR00002.csv".

D50	Control	Ī
D51	Status	İ
D52	Number of Files	<"1"
D53	File Number 1	<"2"

- 1 In D52, store the number of CSV files to transfer "1".
- **2** In D53, store the File Number "2".
- **3** Turn ON D50 bit 1. According to the settings of Condition Number 0, data from 6 words, D100 to D105, are transferred as "ZR00002.". During the data transfer, D51 (Status address) bit 0 (Transferring Bit) turns ON.
- 4 When all files have completed transfer normally, D51 bit 0 turns OFF, and bit 1 (Transfer Complete Flag) turns ON. Turn OFF D50 bit 1.

25.6 Displaying/Editing CSV data on the Screen

25.6.1 Introduction

On the display unit, you can use a CSV Display or File Manager Special Data Display to view data stored on the CF Card or USB storage device. You can use this feature to check the data on the GP.

Displays the CF Card's CSV data on the GP screen.



Display [File Manager]'s display switch and...

You can edit data that displays on the screen by touching it. Also, you can print data to a printer that's connected to the GP unit.

Edit CSV data on the screen.



Touch the cell you want to edit on the Special Data Display [Show CSV] and... The editing screen is displayed

Print CSV data from a printer that's connected to the GP unit.



Touch the print switch on the [Show CSV] and...

CSV data is printed.

25.6.2 Setup Procedure

NOTE	 Please refer to the Settings Guide for details. ^{CP} "25.10.2 [Special Data Display] Settings Guide ■ File Manager" (page 25-83) ^{CP} "25.10.2 [Special Data Display] Settings Guide ■ CSV Display" (page 25-78)
	 For details of the part placement method and the address, shape, color, and label setting method, refer to the "Part Editing Procedure". ⁽³⁾ "8.6.1 Editing Parts" (page 8-44)

Configures the settings to display, edit, and print CSV data stored on the CF Card.

1 From the [Parts (P)] menu, point to [Special Data Display (P)] and select [File Manager (M)]. Place the Part on the screen.



2 Double-click the new Special Data Display [File Manager]. The settings dialog box appears.

💰 Special Data Display					×
Parts ID SP_0000	Basic Switch Display Unit Data Transmission Cature Address Status Address Status Address Action Mode File Operation Target Data CF	Filing	Show CSV	File Manager	
Help (<u>H</u>)			0	K (<u>O</u>) Cancel	

3 In [Action Mode], select [File Operation]. In [Target Data], select [CF].

• To display the data in a USB storage device, from [Target Data], select [CF Card] or [CF <--> USB storage].

4 Click the [Switch] tab. Under [Switch Layout], select the [Display] check box. Select the shape, label and text color. Click [OK (O)].

Parts ID SP_0000 🔆	Basic Switch	
SP_0000 📑	Switch Layout	
Comment	🔽 Display	
	Switch Label	
	Font Type Standard Font 💌	
ABC	Display ASCII	_
	Text Color	
Select Shape		
	Switch Color	
	Border Color 7 🖵 Blink None	•
	Display Color 🗖 2 🚽 Blink None	-
	Pattern None 🗸	

• When you select a switch and press the [F2] key you can directly edit the text on the label.

NOTE

5 Special Data Display Part [File Manager] is now configured. You can move the switches to the appropriate locations.



6 On the same screen as the [File Manager], from the [Parts (P)] menu, point to [Special Data Display (P)] and select [Show CSV (C)]. Place the [Show CSV] on the screen.



7 Double-click the placed Special Data Display [Show CSV]. The following dialog box appears.

Special Data Displ	Basic Display Color Switch
SP_0000 🔅	Display Unit
	Data Transmission Filing Show CSV File Manager
	Edit Data
	Enable Addresses
	Address
	Touch Enable Condition When Bit is ON When Bit is OFF Enable Security Levels
	Level 1
	Status Address
	Status Address
	Get. Operation Log

- 8 Select the [Edit Data] check box.
- 9 Click the [Display] tab. In [Font] set the [Font Type] and [Size]. Select the [Show Column] check box, if necessary.

Basic Display Color	Switch		
-Font			
Font Type	Standard Font	▼ Size	8 x 16 Pixels 👻
Display Language	ASCII	•	
Display Format			

10 Click the [Color] tab. Set the text color and background color.

Basic Display Color	Switch		
Display Color	□7 •	Blink	None
Background Color	0	Blink	None

11 Click the [Switch] tab. Select the check boxes for any necessary scroll or print switches for the Show CSV. Set the number of rows or columns that a scroll switch moves when pressed.

Select the shapes, label and text color. Click [OK(O)].

Select Shape	Basic Display Color Switch Switch Layout Switch Layout Scroll Up Samples to Scroll Scroll Down Samples to Scroll Scroll Left Samples to Scroll Scroll Right Samples to Scroll Print-All Print-Display
	Switch Label Font Type Standard Font Select Switch Display Language ASCI Text Color 7
	Switch Color Border Color 7 V Blink None V Display Color 2 Blink None V Pattern None V
Help (<u>H</u>)	OK (Q) Cancel

• Depending on the switch type, [Switch Color] may be enabled.

• When you select a switch and press the [F2] key you can directly edit the text on the label.

Special Data Display Part [Show CSV] is now configured. Move the switches to the desired locations.



25.6.3 Operating Procedure

Displaying CSV Data

To display data in a Special Data Display [Show CSV], you need a Special Data Display [File Manager] to select files to display.

IMPORTANT	 A Special Data Display [File Manager] appears using a Special Window or Local Window. If the maximum number of windows are already displayed, the File Manager does not appear. Close another window and touch the [File Manager] display switch again. ^{CP} "12.8 Restrictions for Windows" (page 12-29)
NOTE	• Operate CSV data in the USB storage from the [File Manager] for CF/USB storage.

The following display method is intended for CSV data on a CF Card.

1 Touch the File Manager Display Switch to call up [File Manager] on the GP screen.



When the switch is pressed again, the [File Manager] window closes.

The contents of the CF Card's root folder display.



<DIR> displays to the right of the folder name.

Display Area

Displays the folder names and file names on the CF Card in a list.

The files display in the order in which they were created. It is not possible to sort the files by file numbers or time stamps.

Information Area

When you select a folder, the folder creation date displays. Selecting a file displays the creation date and size of the file.

2 Select the folder and then touch the [DISP] key to display the folder contents.



NOTE

• To navigate to a higher hierarchical folder, select the [. DIR] row then touch the [DISP] key.

3 Select a file, and then touch the [DISP] key to view the file in the [Show CSV] dialog box.



- In the [File Manager], if you select files that are not CSV files and then touch the [DISP] key, those files do not appear in the [Show CSV] part.
 - If the CF Card is removed or the cover of the CF Card slot is opened while the CSV file displays, the [Show CSV] dialog box is cleared.
 - Switching screens clears the [Show CSV] display.
You can display all CSV data (Alarm History Data and Sampling Data) created with the GP in the Special Data Display [Show CSV]. The [Show CSV] display works with exclusive scroll switches (Scroll Up, Down, Left, Right).

Special Data Display Part [Show CSV]



NOTE

- You can enter a maximum of 100 characters in each cell.
- Each cell displays as text. The display is fixed as left-aligned.
- Character Code in the CSV File is Native only (press Shift JIS for Japanese).
- The outer borders are 2-dot lines, and the inner borders are 1-dot lines. Twodot spaces are left between the borders that separate the cells and the data in the cells.



• The height of the cell is adjusted depending on the font size. The width of each cell adjusts depending on the text width. When the number of characters is five or less, the width is set to five characters.

How to Move File Manager

The screen position of Special Data Display [File Manager] can be changed.



- 1 Touch the top of the [File Manager] Display.
- 2 Touch the desired position on the screen where you want the display to move.
- **3** The [File Manager] moves to the specified location.

NOTE

• If the [File Manager] Display runs off the screen at a specified position, the coordinates adjust so that the entire window displays.



Editing CSV Data

When the Edit Data feature is set for the Special Data Display [Show CSV], by touching a displayed cell, the editing screen automatically displays. Touch the keypad on the editing screen to directly edit the CF Card or USB storage data.



Touch the [ENT] key after editing data to save the changes and close the editing screen.

- Touching the [CAPS] key allows you to enter lower-case characters. Touching the [CAPS] key again returns to upper-case input mode. The [CAPS] key is cleared when the editing screen closes.
 - The input text on the editing screen displays with the font set to the CSV display. The user cannot change the display color, position, and size because of the fixed system.

Printing CSV Data

Touch the print switch on the Special Data Display [Show CSV] to print the displayed CSV data.

You can print only the portion in the [Show CSV].

• To print data, you must connect a printer to the GP and then configure the printer settings.

Print All

Touch [PRN ALL] for all CSV data on the [Show CSV], including the region not displayed on the screen, to print.



The portion not displayed on the screen

Print-Display

Touch [PRN] to print only the CSV data that displays on the screen.



25.7 Creating Filing Data Recipes

25.7.1 Introduction

Create filing data recipes in GP-Pro EX.

Created data is sent to internal memory or saved to the CF Card inserted in the display unit via a screen transfer.

		Filing	Data	
		Block 0	Block 1	Block 2
	Item Name	Bread	Butter Roll	Croissant
	[PLC1]D00100	350	400	200
	[PLC1]D00101	5	8	4
	[PLC1]D00102	7	8	3
	[PLC1]D00103	12	16	10
	[PLC1]D00104	245	310	120
	[PLC1]D00105	12	40	10
l			*	

NOTE

• You can save the recipe data on a CF Card as well as USB storage device. Transfer Project cannot transfer to a USB storage device placed on the display unit; you must copy the data to the USB storage device manually.

25.7.2 Setup Procedure

NOTE

Please refer to the Settings Guide for details.
 ^{CP} "25.10.1 Common (Recipe) Setup Guide ■ Transferring Filing Data (Filing Data List)" (page 25-65)

The following shows the operation procedure for registering new filing data when multiple folders are not used.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer Filing Data (Filing Data List) (D)]. The following window appears.



- 2 Set the save location for created filing data to [Internal Memory]. Filing data is stored in the GP internal memory via a screen transfer.
 - When you select [CF Card], the CF Card Folder must be set. When you select [USB storage], the USB Storage Destination Folder must be set. The recipe in the CF Card Folder can be transferred to the CF Card in the display unit using the Transfer Project tool. The data in the USB Storage Destination Folder must be copied to the USB storage device manually. You cannot use the Transfer Project tool to transfer to the USB storage device.
- **3** Click [Add]. The [Edit Filing Data] dialog box appears.

💰 Edit Filing D	ata						
File Number		0	3				
Comment							
Storage Start A	ddress	[#INT	ERNALJUSR00	000 💌 🥅	Number of Blocks	3 🗧	🏢 (1 - 165
Display Format		Dec	-	Sign +/-	Number of Data	10 🕂	📕 (1 · 100
Bit Length		16 Bit	-		Language	ASCII	
(Bloc	k0	Block 1	Block 2			
ItemName	Bloc	:k0	Block1	Block2			Option
TERNALJUSF	0		0	0	-		
TERNALJUSED	0		0	0			
TERNALJUSF	0		0	0	-		
TERNALJUSF DI	0		0	0			
TERNALJUSF	0		0	0			
TERNALJUSF DI	0		0	0			
TERNALJUSF 0	0		0	0			
TERNALIUSE	0		0	0			•
						< (0)	Cancel

in [Storage Start Address].

4 In [Storage Start Address], set the start address of the destination (or source) device/PLC. The designated contents are set up in the [Edit Data Area]. Designate the filing data's [Display Format], [Sign +/-], and [Bit Length].

File Number	0 🗄 🏢					
Comment	Ingredient					
Storage Start Address	[PLC1]D00100	▼ 📅	Number of Blocks	3	i -	- 1650)
Display Format	Dec	💌 🔲 Sign +/-	Number of Data	6	🗄 🧮 (1 -	- 10000
Bit Length	16 Bit	•	Language	ASCII		•

NOTE

• If you touch [Option], you can configure setting to transfer data with the item name and block number attached to it.

^(C) "25.12.2 Transferring Item Name and Block Number" (page 25-108)

5 In the [Edit Data Area], enter each recipe name and data.

	Block 0	Block 1	Block 2
ItemName	Bread	Butter Role	Croissant
[PLC1]D00000	350	400	200
[PLC1]D00001		8	4
[PLC1]D00002	7	8	3
[PLC1]D00003	12	16	10
[PLC1]D00004	245	310	120
[PLC1]D00005	12	40	10

6 Click [OK (O)]. The new file is added to the [File List].

📃 🛛 Base 1 (Untitle	ed) 🛛 🗊 Filing D	ata 🗵	4 ⊳
Recipe Settings (Transfer Filing Data)	Go to Mode Settings	
Internal Memory			
File List	Add		
File Number	Comment	Storage Start Address	
0 M	laterial	[PLC1]D00100	

Filing data for File Number "0" is now configured.

25.8 Transferring Recipes (Filing Data) (Using Manual Transfer)

25.8.1 Introduction

On the GP, display a list of the filing data (recipes) stored in backup SRAM. Select which items you want to write to the device/PLC.



Also, device/PLC data overwrites the selected recipes in backup SRAM.



NOTE

- When you transfer from device/PLC backup SRAM, you cannot save as a new recipe. If you do not want to overwrite existing data, create an empty recipe in advance.
- You cannot edit backup SRAM filing data on the GP screen. When transferring via the internal device, you can edit data stored in the internal device by using a Data Display part.

25.8.2 Setup Procedure

NOTE	 Please refer to the Settings Guide for details. ^{CP} "25.10.1 Common (Recipe) Setup Guide ■ Transfer Filing Data (Action Settings)" (page 25-61) ^{CP} "25.10.2 [Special Data Display] Settings Guide ■ Filing Display" (page 25-75)
	 For details of the part placement method and the address, shape, color, and label setting method, refer to the "Part Editing Procedure". ** "8.6.1 Editing Parts" (page 8-44)

On the GP screen's Special Data Display [Filing], the following settings show how to designate and transfer the recipes by touching them.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer Filing Data (Mode) (A)] or click 👔 . The following window appears.



2 Select the [Enable Filing Data Feature] check box.

📃 Base 1 (Untitled) 🔀 🗊 Filing Mode				4 ⊳ ×
Recipe Settings (Transfer Filing Data)	Go to Filing Data Lis	<u>et</u>		
Enable Filing Data Feature				
🥅 Enable multiple folders				
Preparing Transfer (Recipe> SR	AM)		1	
Control Word Address	[PLC1]D00000			
Write Completion Bit Address	[PLC1]X00000	_		
Control Word Address +0	Control			
+1	Folder Number	(When multiple folders are used)		
Control Transfer from Device/P	LC			

3 In [Control Word Address], set the address (D10) to write recipes stored in the display unit internal memory (or CF Card/USB Storage) to backup SRAM. Two consecutive words are used, starting from the set address.

In [Write Completion Bit Address], set the address (M100) to confirm that writing to backup SRAM is complete.

4 Open the screen editor. From the [Parts (P)] menu, point to [Special Data Display (P)] and select [Filing (F)]. Place the Part on the screen.

	••••0•••••••••••	4
-	12345678901234567890123456789012345678901234567890	
- - - 1	2 <u>2</u> 1 3	
-	4 5 6	
-	9	
-	12	

5 Double-click the new Special Data Display. The settings dialog box appears.

💰 Special Data Display		×
Special Data Display Parts ID SP_0000	Basic Display Color Switch Display Unit Data Transmission ID Number Via Internal Device Storage Start Address	Show CSV File Manager File Number File Manager
Help (<u>H</u>)	Remember Cursor Position	OK (Q) Cancel

6 In [ID Number], set the number of the Special Data Display [Filing].

• When displaying multiple Special Data Displays [Filing] on the screen, be sure not to use the same [ID Number].

7 In [File Number], set the file number of the Special Data Display [Filing] you want to display.

All the item names contained in the file designated here can be displayed in a list and transferred.

8 Select the [Display] tab. Set the [Font] and [Display Format].

Font						
Font Type Standar	d Font			Size	8 x 16 Pixels	
Display Format						
Border 💿		° [• 📃	
No Border		Show	Border		Border with Horizontal Lines	
Display Characters	40	-	=			
Display Rows	12		- =			

9 Select the [Color] tab and set the text and background color.

Basic Display Color	Switch		
Display Color	7	Blink	None
Background Color	0	Blink	None 💌
Clear Color		Blink	None 💌

10 Select the [Switch] tab and select the operation switches you want to place. Set the number of rows that a scroll switch moves when pressed. Select the shapes, label and text color. Click [OK (O)].

Parts ID	Basic Display Color Switch
SP_0000 🚊 Comment	Switch Layout
АВС	✓ Transfer from Device/PLC to SRAM ✓ Move Upward Rows to Move 1
	Move Downward Rows to Move
	Switch Label
Select Shape	Font Type Standard Font Select Switch Display ASCII Transfer from SRAM to Device/PLC Language ASCII SRAM Text Color 7 ->PLC
	Switch Color
	Border Color 7 💌 Blink None 💌
	Display Color 📃 2 💌 Blink None 💌
	Pattern None 🔽

NOTE

• Depending on the switch type, [Switch Color] may be enabled.

• When you select a switch and press the [F2] key you can directly edit the text on the label.

Special Data Display Part [Filing] is now configured. You can move the switches to the appropriate locations.



- If you want to save filing data in backup SRAM to the CF Card (or USB Storage), in the System Settings window, select [Display Unit] and click the [Mode] tab. In the [Memory Card Settings] area select the [Save Data] check box and define the [Control Word Address]. The Control Word Address works the same way as saving Alarm History to a CF card.
 - Image: Structure Control Word Address for Data Save" (page 19-58)

25.8.3 Transfer Process

The following shows the process for manual transfer from backup SRAM device/PLC. (When multiple folders are not used.)

1 Turn ON D10 bit 0. All the filing data recipes stored in internal memory are transferred to backup SRAM.

```
• When saving the recipes to the CF Card, turn ON bits 0 and 8. When saving the recipes to the USB storage device, turn ON bits 0 and 9.
```

- 2 When the transfer to backup SRAM has been completed successfully, turn ON the Write Completed Bit (M100). After confirming the bit is ON, turn OFF D10 bit 0 and M100.
- **3** In the Special Data Display [Filing] on the GP screen, files selected in backup SRAM display in a list the item names of registered blocks in File# 0. Touch the recipe you want to transfer. You can select multiple files from the displayed list.
- 4 Touch the SRAM to PLC transfer switch. The selected recipes transfer to the device/PLC.

Special Data Display [Filing]





25.9 Transferring Recipes (Filing Data) Using Automatic Transfer

25.9.1 Introduction

Transfer recipes between the GP backup SRAM and device/PLC by turning ON the address used to control transfer.

• Transfer from Backup SRAM Device/PLC Designate the file no./block no. to transfer and turn ON the control address bit 0. The block data or recipe is written to the device/PLC.



Transfer from Device/PLC το Backup SRAM
 Designate the recipe to transfer and turn ON the control address bit 0 and bit 8. Data from the device/PLC is saved to backup SRAM and overwrites the designated recipe.



• When you transfer from device/PLC to backup SRAM, you cannot save as a new recipe. If you do not want to overwrite existing data, create an empty recipe in advance.

25.9.2 Setup Procedure

```
NOTE
```

 Please refer to the Settings Guide for details.
 [©] "25.10.1 Common (Recipe) Setup Guide ■ Transfer Filing Data (Action Settings)" (page 25-61)

Configure settings to designate the file number/block number and turn ON address D50 bit 0 and transfer the designated recipe.

1 From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer Filing Data (Mode) (A)] or click 📑 . The following window appears.



2 Select the [Enable Filing Data Feature] check box.

Base 1 (Untitled) 🗙 🞒 Filing Mod			4 ▷
ecipe Settings (Transfer Filing Data)	<u>Go to Filing Data L</u>	i <u>st</u>	
🔽 Enable Filing Data Feature			
🔲 Enable multiple folders			
Preparing Transfer (Recipe> SF	(AM)		
Control Word Address	[PLC1]D00000		
Write Completion Bit Address	[PLC1]X00000		
Control Word Address +0	Control		
+1	Folder Number	(When multiple folders are used)	

3 In [Control Word Address], set the address (D10) to write recipes stored in the display unit internal memory (or CF Card/USB Storage) to backup SRAM. Two consecutive words are used, starting from the set address.

In [Write Completion Bit Address], set the address (M100) to confirm that writing to backup SRAM is complete.

4 Select the [Control Transfer from Device/PLC] check box. The transfer settings appear.

Control Transfer from Device/PLC							
└─Transfer Settings (SRAM <	Transfer Settings (SRAM <> Device/PLC)						
Control Word Address		[PLC1]D00000					
Transfer Complete Flag	Transfer Complete Flag Addres						
Control Word Address	+0	Control					
	+1	File Number					
	+2	Block Number					

5 In [Control Word Address], set the address (D50) that controls the transfer between backup SRAM and the device/PLC. Three consecutive words are used, starting from the set address. In [Transfer Complete Flag Address], set the address (M101) used to verify that the transfer is complete.

The automatic transfer settings are configured.

If you want to save filing data in backup SRAM to the CF Card (or USB Storage), in the System Settings window, select [Display Unit] and click the [Mode] tab. In the [Memory Card Settings] area select the [Save Data] check box and define the [Control Word Address]. The Control Word Address works the same way as saving Alarm History to a CF card.

 ^C "19.8.3 Structure ■ Control Word Address for Data Save" (page 19-58)

25.9.3 Transfer Process

Transfer from SRAM to Device/PLC Using One Folder

The following demonstrates how to transfer recipes to the device/PLC.



1 Turn ON D10 bit 0. Filing data recipe stored in internal memory is transferred to backup SRAM.

NOTE

• When saving the recipes to the CF Card, turn ON bits 0 and 8. When saving the recipes to the USB storage device, turn ON bits 0 and 9.

- 2 When the transfer to backup SRAM has been completed successfully, turn ON the Write Completed Bit (M100). After confirming the bit is ON, turn OFF D10 bit 0 and M100.
- **3** In D51, store the File Number "0".
- 4 In D52, store the Block (Recipe) Number "0".
- 5 Turn ON D50 bit 0. The designated data in backup SRAM is transferred to the PLC.
- **6** When the transfer completes successfully, the Transfer Complete Flag (M101) turns ON. After confirming that the bit is ON, turn OFF D10 bit 0 and M100.

Transfer Device/PLC SRAM

The following shows the process for reading the device/PLC data and storing it in File Number "0"/Block Number "1" in backup SRAM.

	Transfer	
D50	Control	
D51	File Number	<"0"
D52	Block Number	<"1"

- 1 In D51, store the File Number "0".
- **2** In D52, store the Block (Recipe) Number "1" where data that is read from the device/PLC is stored.
- **3** Turn ON D50 bit 0 and bit 8. Device/PLC data overwrites block 1.
- 4 When the transfer completes successfully, the Transfer Complete Flag (M101) turns ON. After confirming that the bit is ON, turn OFF D50 bit 0, bit 8, and M101.

25.10 Settings Guide

25.10.1 Common (Recipe) Setup Guide

■ Transfer CSV Data (Condition)

Configure condition and transfer settings for CSV data.

📃 Base 1 (Untitled) 🛛 📆 CSV Cor	ndition 🗵
Recipe Settings (Transfer CSV Data)	Go to CSV File List
🔽 Transfer CSV Data	
Action Mode Condition Action	🔹 Write Mode 🛛 All Files 💽 Language 🛛 ASCII 💽
Control Word Address	🗖 Condition Name Search Feature
	Search Word Address

Transfer CSV DataSelect whether to use the Transfer CSV Data feature.Select the CSV data's transfer action.NOTE• When using a Special Data Display [Data Transmission] with manual transfer. Select [Condition Action].• Condition Action The transfer is executed according to the condition set in [Condition], such as Destination Address or Number of Data Items. You can transfer multiple CSV data recipes at one time.• Address Action The transfer destination and source address is set at transfer time. Change the address for each file and transfer the CSV data.
NOTE• When using a Special Data Display [Data Transmission] with manual transfer. Select [Condition Action].• Condition Action The transfer is executed according to the condition set in [Condition], such as Destination Address or Number of Data Items. You can transfer multiple CSV data recipes at one time.• Address Action The transfer destination and source address is set at transfer time.
Transfer CSV Data Action Mode Address Action Write Mode All Files Control Word Address Destination Device/PLC [PLC1]D00000 PET PLC1 Continued

Setting	Description		
Write Mode	 Defines how to handle overwriting dat All Files Overwrites all the contents of existin will be blank. Overwrite Data Only Overwrites the Time (:DATE) and the CSV file. Other items remain as they 	ng CSV files. ITE ne Value (VALUE	
	 All data from the third row on in the 0 When overwriting, the required avail Storage is at least double the size of 	able space on the the actual CSV f	e CF Card or USB ile.
Control Word Address	Set to operate the CSV data transfer fr automatic transfer. If selected, also set The contents of the set address differ of settings. ^(C) "25.11.2 Control Word Address" (page Condition Action Control Word Address +1 Status +2 Number of Files (n) +3 File Number 1 +4 File Number 1 +2+n File Number n	the address to co lepending on the 25-89) Address A Control Word Address +1 +2 +3 +4 +5 +6 +7 +8 +9 +15	Introl the transfer. [Action Mode] Action Control Status File Number Mode Address Mode Device Code Address Code (2 words) Number of Data Items Reserved Area (7 words)
Language	Select a language for the Condition Name: [Japanese], languages supported by [ASCII], Simplified Chinese, Traditional Chinese, Korean, Cyrillic, and Thai. The Condition Name for the [Data Transmission] follows this setting.		
Condition Name Search Feature	When [Condition Action] is set to [Transfer Mode] and automatic transfer is used, specify whether to use the Condition Name Search feature. The Condition Name Search feature searches for CSV files by condition name and writes all matching files from the CF Card/USB to Device/PLC.		

Continued

Setting	Description			
Search Word Address	text. This can be address. The lower 1 address) are transfer. Th A file whos CF Card/US T25.11.3 Search S NOTE • The searc the condit errors. • When dat files displ	set to either 6 words of the e used, and the e condition so e condition no SB storage an About the Con Storage Method h is only post tion name. Sp a transfer is c ays. The last evice Special	a device/l a device/l ne address ey store tl earch nan ame mato ad is trans idition Nan ds" (page 2 sible whe baces indi completed transferro	ch, set a word address to store the search PLC address or GP internal device a designated here (or 8 words for a 32 bit he condition name of the file you want to he can be up to 32 characters. The stored string is detected in the ferred. he Search Feature ♦ Condition Name
		LS9200	LS Area	File Number of last transferred CSV file File Number of last transferred CSV file
Destination Device/ PLC	When [Action Mode] is [Address Action], select the device/PLC for transfer.			
Condition	NOTE	-	ht-click r Open th and edit The [CS appears Copy the Add the Delete t Ensures condition	nenu can edit the list. Description e [CSV Data Transfer Condition] Dialog Box the condition selected in the [Condition List]. V Data Transfer Condition] dialog box also by double-clicking the cell. e condition selected in the [Condition list]. copied condition into the [Condition list]. he condition selected in the [Condition list]. that the file number settings for the n are not duplicated. If file numbers are d in several conditions, data are transferred
Create	Creates a ne	ew condition. dialog box ap	accordir Click the	e hyperlink and the [CSV Data Transfer

♦ [CSV Data Transfer Condition] Dialog Box

Condition Tab

💰 CS¥ Data Transfer C	ondition 🛛 🗙
Condition Extended	
Condition Number (Group Number)	0 🔁 🏢
Condition Name (Group Name)	
Destination	
Destination Word Address	[PLC1]D00000
Number of Data	1 🗄 🏢
Data Type	Dec 💌 🗖 Sign +/-
Bit Length	16 Bit
File Number	
Start	0 🕂 🏢
End	65535 🛨 🏢
	OK (0) Cancel

S	Setting	Description
Condition Number (GROUP NUMBER)Designate the condition number. The setting range is from 1023. Assign each condition its own unique number.		Designate the condition number. The setting range is from 0 to 1023. Assign each condition its own unique number.
Condition Name (GROUP NAME)		Condition names can have a maximum of 32 characters. When transferring device/PLC to CF/USB, the CSV file condition name is defined here.
	Destination Word Address	The specified address functions as the destination address (or as the source address when transferring from the device/PLC to the CF Card/USB storage device). An internal device address can also be set.
	Number of Data Items	Set the number of data transfer units from 1 to 10000.
Destination	Data Type	Select the data type of the transfer data from [Dec], [Hex], or [Float]. NOTE • If [Float] is selected, [Bit Length] is fixed to [32 Bits].
	Sign +/-	Set to allow negative numbers. This is available only when the [Display Format] is [Dec].
	Bit Length	Choose the bit length from [16 Bit] or [32 Bit].
		Set the file range to register as a single condition with file numbers. The setting range is from 0 to 65535. All the files from [Start] to [End] become part of the same group.
File Number	Start/End	 NOTE Please do not set the same file number to multiple conditions. If file numbers repeat in several conditions, the files are transferred according to the condition with the smallest number.

Extended

When automatically transferring from the device/PLC to the CF Card or USB storage device, you can automatically assign file numbers to create new files. This has no effect on automatic transfers from the CF Card or USB storage to the device/PLC.

5¥ Data Transfer Condi	tion		
dition Extended			
ile Number			
Automatically Assign F	ile Numbers		
- <u>199</u> sterne matter setters			
Resume Bit Addres	3		
Full Bit Address			
1			
SV Data Output			
Round Off			
Digits 17 🕂 🏙	Decimal Pl	laces 8	-
	D COMMUNITY	10	

Setting	Description
Automatically Assign File Numbers	Enable this feature when reading data from the device and saving to a CF Card/USB storage as a CSV file. Numbering occurs until the designated [End]. After that, data is not transferred. To overwrite existing files and continue transferring, use [Loop] or [Resume Bit Address].
Loop	If enabled, when the File Number reaches the designated [End], the oldest file is deleted and files are overwritten in order beginning with [Start] when a new file is created. Enable the loop action.
Resume Bit Address	Designate whether or not to set a bit address to resume transmission when the file number has reached the designated [End]. When this bit address is turned ON and after the [Control Word Address] is turned ON, files are created from the designated [Start].
Full Bit Address	Confirms that the file number has reached the designated [End]. This bit address turns ON when File Number reaches the [End].
CSV Data Output	 Defines how to format data when output to a CSV file. This setting is available only when the [Data Type] in the Condition is set to [Float]. Round Off Sets whether to round off digits. Numbers are truncated if not rounded. Digits/Decimal Places In the [Digits] field, define the number of digits from 1 to 17. This includes the number of [Decimal Places]. The allowable range for [Decimal Places] should be less than the value set in [Digits].

■ Transferring CSV Data (CSV File List)

Recipe Settings (Transfer CSV Data) Go to Condition Settings							

Setting	Description			
Save in	 Select the destination to save from [CF Card] or [USB Storage]. CF Card The CF Card Folder needs to be specified. The data in this folder can be transferred to the CF Card in the GP by transfer project. USB storage The USB Storage Destination Folder must be specified. The data in this folder must be manually transferred to the USB storage device. 			
Listed Items	 Select the displayed contents from the [CSV File List]. Show Detail Condition Name and Number of Data Items settings display along with the file name. File Name Only the file name displays. 			
Show Details	The CSV File registered in GP-Pro EX displays as a list. NOTE • The shortcut key or right-click menu can edit the list.			
Update	Update the contents in [CSV File List].			
Add	Register a new file. The file number can be any number from 0 to 65535 that is not in use. Click [OK (O)]. The [Edit CSV File] dialog box appears.			

♦ [Edit CSV File] Dialog Box

		0 🔅	<u></u>	Numbe	er of Data
	Title		Value	1	
1	1100		1000		0
2					0
3					0
4					0
5					0
6					0
7					0
8					0
9					0 💌
			OK (0)	Ca	incel

Setting	Description					
Condition Number (GROUP NUMBER)	Set the cond	Set the condition number. The setting range is from 0 to 1023.				
Condition Name (GROUP NAME)		Set the condition name with a maximum of 32 characters. When a Special Data Display [Data Transmission] is used, the condition name set here displays.				
Number of Data Items	Set the num	ber of recipe	data from 1 to 10000.			
	device/PLC		data. The title set here is not transferred to the ht-click menu can edit the list.			
Edit Data Area	Names of features	Shortcut	Description			
	Сору	Ctrl + C	Copies the contents of the currently selected cell.			
	Paste	Ctrl + V	Pastes the copied contents into the selected cell.			
	Clear	Delete	Deletes the contents of the currently selected cell.			
	Select All	Ctrl + A	Select all cells in [Edit Data Area].			

Transfer Filing Data (Action Settings)

📃 Base 1 (Untitled) 🗙 🗊 Filing Mod	e 🗙	$\triangleleft \triangleright {\sf X}$
Recipe Settings (Transfer Filing Data)	<u>Go to Filing Data List</u>	
Enable Filing Data Feature		
🥅 Enable multiple folders		
Preparing Transfer (Recipe> SI	RAM)	
Control Word Address	[PLC1]D00000	
Write Completion Bit Address	[PLC1]X00000	
Control Word Address +0 +1	Control Folder Number (When multiple folders are used)	
Control Transfer from Device/		

Enable Filing Data Feature Select to transfer filing data. Enable Multiple Folders Select to create multiple folders. In the backup SRAM, specify the word address to write the recipe to. The address bit 0 turns ON and writes data to the backup SRAM. Use bit 8 and bit 9 to set the transfer operation. 15 9 8 7 10 Reserved (0) Mode 0 - 1 Write to Backup SRAM O Internal Memory -> SRAM 0 0 1 0 Word Address Important * This address is not turned OFF automatically. After the [Write Completion Bit Address] turns ON, turn OFF bit 0. • When using multiple folders, two words are used starting from the designated address. Store the folder number (1 - 8999) to write to backup SRAM, then turn ON bit 0 of the control address. However, only one folder can be stored in backup SRAM.	Set	tting	Description
Preparing Transfer (Recipe -> SRAM) Control Word Address SRAM) Control Word Address In the backup SRAM, specify the word address to write the recipe to. The address bit 0 turns ON and writes data to the backup SRAM. Use bit 8 and bit 9 to set the transfer operation. 15 9 8 7 10 Image: Control Word Address Address 0 1 1 Control Word Address 0 1 1 Reserved 0 1 1 Reserved 0 1 1 Reserved 1 1 Reserved 0 0 0 1 0 0 0 0 1 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	J		Select to transfer filing data.
Preparing Transfer (Recipe -> SRAM) Control Word Address Control Word Address Image: Control of the control address is not turned OFF automatically. After the [Write Completion Bit Address] turns ON, turn OFF bit 0. • When using multiple folders, two words are used starting from the designated address. Store the folder number (1 - 8999) to write to backup SRAM, then turn ON bit 0 of the control address is not word Address	Enable Mul	tiple Folders	Select to create multiple folders.
Continued	Transfer (Recipe ->	Word	The address bit 0 turns ON and writes data to the backup SRAM. Use bit 8 and bit 9 to set the transfer operation. 15 9 8 7 10 Reserved (0) 0 \rightarrow 1 Write to Backup Bit 9 Bit 8 0 0 Internal Memory \rightarrow SRAM 0 1 CF Card \rightarrow SRAM 1 0 USB Storage \rightarrow SRAM 1 1 Reserved WPORTANT • This address is not turned OFF automatically. After the [Write Completion Bit Address] turns ON, turn OFF bit 0. • When using multiple folders, two words are used starting from the designated address. Store the folder number (1 - 8999) to write to backup SRAM, then turn ON bit 0 of the control address. However, only one folder can be stored in backup SRAM.

Set	ting	Description					
Preparing Transfer (Recipe -> SRAM)	Write Completion Bit Address	Set the Bit Address to verify when the data write to backup SRAM completes. When recipe data is stored correctly in backup SRAM, this bit turns ON. After confirming completion, turn OFF this address. MPORTANT • When the recipes cannot be transferred to the backup SRAM, bit 9 of the display unit's internal device LS2032 turns ON.					
Control Transfer from Device/PLC		Set to control the filing data transfer by the device/PLC (automatic transfer).					
		NOTEFor manual transfer, this setting is not required.					
Transfer Settings (SRAM <- ->Device/ PLC)	Control Word Address	Set the word address that controls the transfer between backup SRAM and the device/PLC. Three consecutive words are used, starting from the designated address. Control Word Address $\begin{array}{c c} Control \\ +1 \\ +2 \end{array}$ Block Number After designating the File Number/Block Number, the transfer starts when this address' bit 0 turns ON. The transfer destination is set in bit 8 $\begin{array}{c c} 15 & 9 & 8 & 7 \\ \hline & & & & \\ 15 & & & 9 & 8 & 7 \\ \hline & & & & & \\ 15 & & & & & \\ \hline & & & & & \\ \hline & & & & & \\ \hline & & & &$					
	Transfer Complete Flag Address	 the [Transfer Complete Flag Address] is ON, turn OFF bit 0. Set the bit address that verifies that the data transfer between backup SRAM and the PLC is completed. When the transfer completes successfully, this bit turns ON. After confirming completion of the transfer, turn OFF this address. IMPORTANT If data transmission backup SRAM device/PLC cannot be run, the 0 internal device LS2032 bit 10 turns ON. 					

Transfer Preparation Timing Chart

When the Control Word Address bit 0 turns ON and filing data is correctly stored in backup SRAM, the [Write Completion Bit Address] turns ON. After confirming completion, turn OFF this bit.



If data cannot be transmitted to backup SRAM due to insufficient memory, the internal device (Special Relay Area) LS2032 bit 9 is turned ON. To transfer data again, turn OFF the [Control Word Address] bit 0 temporarily. Then, after setting the communication cycle time as either your standard communication cycle time or 150ms (whichever is longer), turn it ON.



Automatic Transfer Timing Chart

When the designated [Control Word Address] bit 0 turns ON and filing data is correctly transferred, the [Transfer Complete Flag Address] turns ON. After confirming completion, turn OFF this bit.



If data cannot be transmitted between the PLC and backup SRAM internal device Special Relay Area LS2032 bit 10 turns ON. To transfer data again, turn OFF the [Control Word Address] bit 0 temporarily. Then, after setting the communication cycle time as either your standard communication cycle time or 150ms (whichever is longer), turn it ON.



■ Transferring Filing Data (Filing Data List)

When multiple folders are not used

📮 Base 1 (Untitle	d) 🗵 🗊 Filing l	Pata 🗵	4 ▷				
Recipe Settings (T	Recipe Settings (Transfer Filing Data) Go to Mode Settings						
Internal Memory	•						
File List	Add						
File Number	Comment	Storage Start Address					

Setting			Description		
Save in	 Select to save filing data in [Internal Memory], [CF Card], [USB storage]. Internal Memory Save recipe data in the display unit's internal memory using the Transfer Project tool. CF Card The CF Card Folder needs to be specified. The data in this folder is transferred to the CF card in the display unit using the Transfer Project tool. USB storage The USB Storage Destination Folder must be specified. The data in this folder must be manually transferred to the USB storage device. It cannot be transferred using the Transfer Project tool. 				
	recipes.		ber and storage start address of the registered at-click menu can edit the list. Description		
File List	Edit	Ctrl + E	Open the [Edit Filing Data] dialog box and edit the file selected in the [File List]. The [Edit Filing Data] dialog box also appears by double-clicking the cell.		
	Сору	Ctrl + C	Copies the file selected in [File List].		
	Paste	Ctrl + V	Pastes the copied file into a new file in [File List]. The smallest available file number is allotted to the new file.		
	Delete	Delete	Deletes the selected file.		
Update	Updates the	summary that	t displays in [File List].		
Add	Adds the recipes as a new entry. Click to open the [Edit Filing Data] dialog box. ☞ " ◆ [Edit Filing Data] Dialog Box" (page 25-67)				

When multiple folders are used

If [Enable Multiple Folders] is selected, the [Folder List] displays. From the [Common Settings (R)] menu, point to [Recipe (R)] and select [Transfer Filing Data (Mode) (A)].

💻 Base 1 (Untitled	📔 🔝 🗊 Filing Da	ta 🖸 🇊 Filing Mode 🛛	4 ⊳
Recipe Settings (Tra	ansfer Filing Data)	Go to Mode Settings	
Internal Memory	•		
Folder List	Add		
Folder Number	Comment		
File List	Add		
File Number	Comment	Storage Start Address	

Setting		Description				
	Displays a list of registered folder numbers, which is the **** portion of the file name "F****.bin".					
	• The shortcut key or right-click menu can edit the list.					
Folder List	Names of Shortcut features	Description				
	Edit Ctrl + E	Edit the folder number and comment for the selected folder.				
	Copy Ctrl + C	Copy the selected folder.				
	Paste Ctrl + V	Pastes the copied folder into a new folder in [Folder List].				
	Delete Delete	Deletes the selected folder.				
Add	Creates a new folder to be saved. Click to open the [Add Folder] dialog box.					
Folder Number		he ***** portion in the file name *****.bin from1 or that hasn't already been used.				
Comment	Set a folder title of up to	Set a folder title of up to a maximum of 30 characters.				

♦ [Edit Filing Data] Dialog Box

💰 Edit Filing 🛙	Data							×
File Number		0	3 1					
Comment								
Storage Start A	ddress	[#INT	[ERNAL]USR	00000	-	Number of Blocks	3	🛨 🏢 (1 - 1650)
Display Format		Dec		•	Sign +/-	Number of Data	10	🛨 🏢 (1 - 10000)
Bit Length		16 Bi	it	•		Language	ASC	
	Bloc	kO	Block 1		Block 2			
ItemName	Bloc	k0	Block1		Block2	-		Options
TERNALJUSR0	0		0	0		-		
TERNALJUSR0	0		0	0				
TERNALJUSR0	0		0	0				
TERNALJUSR0	0		0	0				
TERNALJUSR0	0		0	0				
TERNALJUSR0	0		0	0				
TERNALJUSR0	0		0	0				
TERNALIUSRO	0		0	0				T
						0	IK (0)	Cancel

Setting	Description	
File Number	Set the file number. The value can be from 0 to 2047.	
Comment	Set a comment of up to 32 characters.	
Storage Start Address	In [Storage Start Address], set the start address of the destination (or source) device/PLC.	
Display Format	 Choose the data display type from [Dec], [BCD], [Hex], or [Float]. NOTE If [Float] is selected, [Bit Length] is fixed to [32 Bits]. 	
Sign +/-	Set to allow negative numbers. This can only be set when the [Display Format] is [Dec].	
Bit Length	Choose the data bit length from [16 Bit] or [32 Bit].	
Blocks	Set the number of blocks (recipes) to register in the file. Up to 1650 blocks can be saved in one file. The number of blocks that can be set depends on the [Number of Data Items].	
Number of Data Items	Set the number of data per block. The number of data can be a maximum of 10000 (or 5000 when the data is 32 bit). The number of data that can be set depends on the [Number of Blocks].	
Language	Select a language for the Item Name of filing data: [Japanese], languages supported by [ASCII], Simplified Chinese, Traditional Chinese, Korean, Cyrillic, and Thai. The Item Names in the [Filing] follow this setting.	

Continued

Setting	Description				
	In each block, enter the recipe title and data. The data range depends on				
	the [Bit Length] and [Sign +/-].				
	Bit Length	Data Type	Sign +/-	Input Range	
		Dec	Uncheck ed	0 to 65535	
	16 bit		Checked	-32768 to 32767	
		Hex		0FFFF(h)	
		BCD		0 to 9999	
		Dec	Uncheck ed	0 to 4294967295	
			Checked	-2147483648 to 2147483647	
Edit Data Area	32 bit	Hex		0FFFFFFF(h)	
Euli Dala Alea		BCD		0 to 99999999	
		Float		-9.9e16 to 9.9e16	
	PasteCtrl + VPasteClearDeleteDelete		Description es the contents of the currently selected cell. es the copied contents into the selected cell. tes the contents of the currently selected cell. ct all cells in [Edit Data Area].		
Option	 Displays the [Preferences] dialog box. Configure settings for transfer. "25.12.2 Transferring Item Name and Block Number" (page 25-108) Send Item Names Send Block Number Caution: When "Viant of the special data display is enabled, even if "Send Item Names" is OFF, item names are transferred to the internal device area. OK O Cancel Send Item Names Select whether to transfer the item names when data transfers. Send Block Number Select whether or not to transfer the block numbers when data transfers. 				

25.10.2 [Special Data Display] Settings Guide

💣 Special Data Display			×
SPEcial Data Uspray	Basic Display Color Switt Display Unit Data Transmission Fili Transfer Status Address	csv	File Manager
Help (<u>H</u>)			OK (Q) Cancel

Setting	Description
Parts ID	Parts are automatically assigned an ID number. Special Data Display ID: SP_**** (4 digits) The letter portion is fixed. You can change the number portion within the range of 0000-9999.
Comment	The comment for each Part can be up to 20 characters.
Display Unit	 Select which type to use. Data Transmission Displays the CSV data recipe Condition Names in a list and transfers the selected recipe from the CF Card /USB storage to the device/PLC. Image Transmission" (page 25-70) Filing Displays the recipe filing data in a list on the screen, and transfers the selected recipe from the display unit backup SRAM to the device/PLC. Image Transmission" (page 25-75) Show CSV *2 Displays the CSV data (e.g., recipe data, alarm history data, sampling data) saved on the CF Card/USB storage. You can also edit or print the data. The [File Manager] and [Data Transmission] display parts are used together. Image The File Manager displays folders and files saved in the CF Card /USB storage on the display unit. You can copy data between the CF Card or the FTP Server. Image The File Manager" (page 25-83)

Data Transmission

Displays a list of the recipe data (CSV data) condition names on the display unit. Transfers the selected data between the CF Card/USB storage and the device/PLC.

Basic

Basic Display Color	Switch			
Display Unit				
Data Transmissior	Filing	CSV Show CSV	File Manager	
Transfer Status	ldress			

Setting	Description			
Transfer Status	Select an address to verify the transfer state and result status during the transfer.			
	Set the address where the transfer status and result are stored.			
	Transfer Status Address	Reserved (0)		
		rror Status Transfer Completed		
	Error Codes (Results ref	ected in the error status bits)		
	0 Completed Successfully	Transfer completed successfully.		
	1 Reserved	-		
Transfer Status Address	² No Transfer Condition Number	For transfer, the Condition Number that corresponds to the specified File Number (GROUP NO) does not exist.		
	3 Internal Device Range Error	In the CF Card/USB storage to device/PLC data transfer where the start address of the transfer is specified to the internal device, data transfer was attempted for an address outside the specified range of the internal device.		
	4 No CF Card or USB Storage	The CF Card/USB storage is not inserted in the GP, or the CF Card cover is not closed.		
	⁵ Read Error	The read-out from the CF Card/USB storage failed in the CF Card/USB storage to device/PLC data transfer.		
	6 Write Error	Data writing failed in the device/PLC to CF Card/ USB storage data transfer, or there is not enough available space.		
	7 CF Card Error/ USB Storage Error	The CF Card/USB storage device is invalid, unformatted, or the media inserted is not a CF Card/ USB storage device.		
		Continued		

Setting	Description		
	8 Reserved	-	
	9 Reserved	-	
	10 Reserved	-	
Transfer Status Address	11 No Condition	Without the [Enable Data Transmission Feature] settings, a CSV file tries to display on the CSV display from a CF Card/USB storage.	
	¹² Write Error	Data writing from CF Card/USB storage data transfer failed on the PLC.	
	¹³ Read Error	Data reading from CF Card/USB storage data transfer failed on the PLC.	

Manual Transfer Timing Chart

Touch the transfer switch and the [Transfer Status Address] Transferring bit (bit 0) turns ON. When a data transfer is completed successfully, the Transferring bit turns OFF and the Transfer Completion bit (bit 1) turns ON. After confirming that the transfer is completed, turn the Transfer Complete Bit OFF.



• The Transfer Complete Flag (bit 1) is not turned OFF automatically. Turn it OFF from the device/PLC.

Display

Basic Display Color S	witch		
Font Font Type Standar	d Font 💽 Siz	e 8 x 24 Pixels 💌	
Display Format Border 💿	c 🗌	• 📃	
No Border	Show Border	Border with Horizontal Lines	
Display Characters	40 📰 🏢		
Display Rows	12 📑 🔳		

Setting	Description	
Font Type	 Choose a font type for the characters and numeric values from [Standard Font] or [Stroke Font]. Standard Font This is a Bitmap font. Choose the character height and width magnification ratio. When you magnify/shrink characters, the outline may become rough or the letter may appear compressed. Stroke Font This is an outline font where the ratio of the character height/width is fixed. The letters will have a smooth outline even if you magnify/shrink them. However, this font uses more disk space on the GP. 	
Size	 Select a font size for the format of characters and numeric values. Standard Font: [8 x 8 pixels] to [64 x 64 pixels] in 8 pixel increments. You can use fixed font sizes [6 x 10 pixels], [8 x 13 pixels], and [13 x 23 pixels] for characters. Stroke Font: 6 to 127 pixels 	
Border	Select the type of data border.	
Display Characters	Set the number of characters to display on each line from 1 to 100.	
Display Rows	Set the number of lines to display from 1 to 50.	
Color

Basic Display Color	Switch		
Display Color	7 -	Blink	None
Background Color	0	Blink	None
Clear Color		Blink	None

Setting	Description		
Display Color	Select a color for the displayed text.		
Background Color	Set the background color.		
	Select the blink and blink speed. The [Display Color] and [Background Color] can be set up with different blink settings.		
Blink	 NOTE There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. ^{CP} "8.5.1 Setting Colors ■ List of Compatible Colors" (page 8-36) 		

Switch

Set the switches attached to the Data Transmission Display.

💰 Special Data Display	×
Parts ID SP_0000 Comment	Basic Display Color Switch Switch Layout Transfer from CF/USB to Device/PLC Transfer from Device/PLC to CF/USB Scroll Up Samples to Scroll Scroll Down Samples to Scroll Display
Select Shape	Switch Label Font Type Standard Font Select Switch Display Language ASCI Transfer from CF/USB to Device/PL CF-> Switch Color
	Border Color 7 V Blink None V Display Color 2 V Blink None V Pattern None V
Help (<u>H</u>)	OK (Q) Cancel
NOTE • Depending	g on the switch type, [Switch Color] may be enabled.

• Depending on the switch type, [Switch Color] may be enabled.

• When you select a switch and press the [F2] key you can directly edit the text on the label.

S	etting	Description			
Part Shape		Displays the switch shape.			
Select Shape		Open the [Select Shape] dialog box to choose the switch shape.			
	Transfer from CF/ USB to Device/PLC	Select to place a switch to transfer CSV data from CF Card/USB storage to the device/PLC.			
	Transfer from Device/PLC to CF/USB	Select to place a switch to transfer CSV data from the device/PLC to the CF Card/USB storage.			
Switch Layout	Scroll Up	Select to place a switch to scroll up the Data Display. If you touch this switch while CSV data is selected, the selection cancels.			
	Scroll Down	Select to place a switch to scroll down the Data Display. If you touch this switch while CSV data is selected, the selection cancels.			
	Samples to Scroll	When the [Scroll Up] and [Scroll Down] switches are placed, designate how many rows they scroll when pressed. The setting range is from 1 to 100.			
	Display	Select to place a switch to display selected CSV file in the [Show CSV] Display. If you touch this switch when multiple CSV files are selected, the top CSV file displays in the [Show CSV].			
	Font Type	Choose the label font for the switches from [Standard Font] or [Stroke Font].			
Switch Label	Display Language	Select a language for the label on the switch: [Japanese], [ASCII], [Chinese (Traditional)], [Chinese (Simplified)], [Korean], [Cyrillic Alphabet], or [Thai]			
	Text Color	Select the font color that will display on the switch labels.			
	Select Switch	Select the switch that you want to type a label for.			
	Label	Enter the text that you want to display on the switch selected in [Select Switch].			
	Border Color	Select a border color for the Switch.			
	Display Color	Set the switch color.			
	Pattern	Select the switch pattern from 9 types.			
Switch Color	Pattern Color	Select the switch pattern color.			
	Blink	 Select the blink and blink speed. [Font Color], [Border Color], [Display Color] and [Pattern Color] can be set up with different blink settings. NOTE There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. * "8.5.1 Setting Colors = List of Compatible Colors" (page 8-36) 			

Filing Display

Display recipe filing data in a list on the screen and transfer the selected data between the GP backup SRAM and device/PLC.

Basic

Basic Display Color Switch	
Display Unit	CSV Show CSV File Manager
ID Number 0	File Number 0
🕞 Via Internal Device 🛛 ————	Transfer Complete Flag
Storage Start Address	Inter-PLC Transfer Complete Bit Address
✓ Direct Selection	
🔽 Remember Cursor Position	

Setting	Description
ID Number	An ID number related to the [Filing] Display and a Switch Lamp [Special Switch] [File Item Switch]. The value can be between 0 and 255. When placing two or more [Filing] Displays on one screen, ensure that this number is unique.
File Number	Designate the filing data number to display in the [Filing] Display from 0 to 2047.
Via Internal Device	Set to transfer via the internal device when transferring filing data. By temporarily storing filing data in the internal device, you can use a Data Display to view and edit data on the GP screen. "" "25.12.3 Manual Transfer Via the Internal Device" (page 25-110) NOTE • While filing data is transferred between SRAM and the internal device, the GP internal device Special Relay Area LS2032 bit 11 is turned ON.
Storage Start Address	When [Via Internal Device] is set, select a start address for data stored there.
Transfer Complete Flag	Set to confirm that transfer SRAM device/PLC is complete with a designated bit.
Inter-PLC Transfer Complete Bit Address	 Set the bit address to confirm that transfer is complete. NOTE If data transmission cannot be performed, this bit stays OFF, and the internal device Special Relay Area LS2032 bit 10 turns ON.
Direct Selection	To select data to transfer, touch displayed item names. Or, use the up/down cursor switches to select item names.
Remember Cursor Position	Set to save the current cursor position when a screen change occurs.

Display

Same as for a Special Data Display [Data Transmission]. [™] "25.10.2 [Special Data Display] Settings Guide ◆ Display" (page 25-72)

Color

Same as for a Special Data Display [Data Transmission]. [™] "25.10.2 [Special Data Display] Settings Guide ◆ Color" (page 25-73)

Switch

Set the switches attached to the Filing Display.

	Setting	Description	
Par	t Shape	Displays the shape that you chose for the switch with [Select Shape].	
Sele	ect Shape Open the [Select Shape] dialog box to choose the switch shape.		
	Transfer from SRAM to Device/PLC	Select to place a switch to transfer filing data from backup SRAM to the device/PLC.	
Switch Layout	Transfer from Device/PLC to SRAM	Select to place a switch to transfer filing data from the device/PLC to backu SRAM.	
	Move Upward	Select to place a switch to move the cursor up.	
Switc	Move Downward	Select to place a switch to move the cursor down.	
	Rows to Move	When you place a [Move Upward] or [Move Downward] switch, enter how many rows to move when pressed. The setting range is from 1 to 2048.	

Continued

	Sotting	Description		
	Setting			
	Font Type	Choose the label font for the switches. [Standard Font], [Stroke Font] can be selected.		
Switch Label	Display Language	Select a language for the label on the switch: [ASCII], [Japanese], [Chinese (Traditional)], [Chinese (Simplified)], [Korean], [Cyrillic Alphabet] or [Thai].		
/itch	Text Color	Select the font color that will display on the switch labels.		
Š	Select Switch	Select the switch that you want to type a label for.		
	Label	Enter the text that you want to display on the switch selected in [Select Switch].		
	Border Color	Select a border color for the Switch.		
	Display Color	Set the switch color.		
	Pattern	Select the switch pattern from 9 types.		
Switch Color	Pattern Color	Select the switch pattern color.		
	Blink	 Select the blink and blink speed. You can choose different blink settings for the [Display Color], [Pattern Color], [Border Color], and [Text Color]. NOTE There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. * "8.5.1 Setting Colors List of Compatible Colors" (page 8-36) 		

 Depending on the switch type, [Switch Color] may be enabled. When you select a switch and press the [F2] key you can directly edit the text on the label.
on the label.

CSV Display

Displays CSV data (such as recipe data, alarm history data, sampling data) saved on the CF Card or USB storage. You can also edit or print the data.

The [File Manager] and [Data Transmission] display parts are used together.

Basic

			101 101 100 100 100 100 100 100 100 100	
ata Transmission	Filing	Show CS	V F	ile Manager
Edit Data				
Interlock Feature				
🔲 Enable Addresse	es			
Address [-	
Touch Enable (Condition (When Bit is 0		/hen Bit is OFF
Enable Security	Levels			
Level	1 🚊			
Status Address —				
atus Address			-	

Setting	Description				
Edit Data	Select to edit data in the CSV Display. When selected, specify whether to use an address and security level when touching the cell of data you wish to edit.				
Interlock feature	When [Edit Data] is designated, select whether to use an address and security level for the Interlock feature (allows data editing only when a condition is satisfied).				
Enable Addresses	This function allows editing of data only when it is in a state that has been selected via [Touch Enable Condition]. Select the check box to use Interlock.				
Address	Specify the bit address that presents an Enable condition for the cell touch. Touch is enabled (disabled) depending on the state of this address.				
	Select the condition that enables the cell touch.				
	Touch Enable Condition	Address Status	Touch Enabled/ Disabled		
Touch Enable Condition	When Bit is ON When Bit is	ON	Touch enabled		
		OFF	Touch disabled	-	
		ON	Touch disabled		
	OFF	OFF	Touch enabled		

Continued

Setting	Description			
	Select to use the security function for the part. When logged in with a level higher than the security level set for the part, the touch action will be			
Enable Security Levels				
	enabled.			
Level	Set the security level of the part within the range of 1 to 15.			
	When editing or printing data, designate whether or not to confirm the			
	status and error contents with the designated address.			
	Set the word address to store the current status of data editing and printing.			
	<u>15 12 11 2 1 0</u>			
	Reserved (0) Edit Data Outputting Bit			
	Error Status Printing Bit			
	Error Codes (Reflected in the error status bits)			
	0 Completed Successfully Transfer completed successfully.			
	1 Reserved -			
	2 Reserved -			
	3 Reserved -			
Status Address	4No CF Card or USB StorageThe CF Card/USB storage is not inserted in the GP, or the CF Card cover is not closed.			
	5 Read Error Read-out from the CF Card/USB storage failed.			
	6Data writing from CF Card/USB storage failed, or space is unavailable.			
	7 CF Card Error/ The CF Card/USB storage device is invalid			
	USB Storage or the media inserted is not a CF Card/USB			
	Error storage device.			
	8 Reserved -			
	 Edit Data Outputting Bit This bit is turned ON when you press the "ENT" key on the CSV data editing screen. It remains ON while the CSV data is read to the CF Card/ USB storage. While the edited data is output, other cell data cannot be printed or edited. Printing Bit This bit is turned ON. While printing, the data cannot be edited or printed. 			
	Specify whether to record the operation log. It can be specified only when selecting the [Edit Data] check box.			
Get Operation Log When [Enable Operation Log Function] is not selected in the consettings [Operation Log Settings], the message "Unable to read operation log of each part" will appear. Select [Unable Operation Function] to enable the operation log settings.				

Display

Basic Display Color	Switch						
Font	Font						
Font Type	Standard Font 💌	Size	8 x 16 Pixels 🗨				
Display Language							
Display Format							

Setting	Description
	Choose a font type for the CSV data.
	Standard Font
	This is a Bitmap font. Choose the character height and width magnifica-
Font Type	tion ratio. When you magnify/shrink characters, the outline may become rough or the letter may appear compressed.
	Stroke Font
	This is an outline font where the ratio of the character height/width is
	fixed. The letters will have a smooth outline even if you magnify/shrink
	them. However, this font uses more disk space on the GP.
	Select a font size for the CSV data.
	Standard Font: [8 x 8 pixels] to [64 x 64 pixels] in 8 pixel increments. You
Size	can use fixed font sizes [6 x 10 pixels], [8 x 13 pixels], and
	[13 x 23 pixels] for characters.
	Stroke Font: 6 to 127 pixels
Display Language Select a language for the CSV data.	
Show Column	Select to display the row number and column number in the [Show CSV].
	The column portion cannot be edited or printed.

♦ Color

Basic Display Color	Switch		
Display Color	7	Blink	None
Background Color	0	Blink	None

Setting	Description		
Display Color	Select a color for the displayed text.		
Background Color	Set the background color.		
Blink	Select the blink and blink speed. You can choose different blink settings for the [Display Color], and [Background Color].		
	 There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. ** "8.5.1 Setting Colors List of Compatible Colors" (page 8-36) 		

Switch

Configure settings for the switches (Scroll switches, Print switch) attached to the CSV Display.

Parts ID SP_0001 📫	Basic Display Color Switch		
Comment	Switch Layout		
	🔽 Scroll Up	Samples to Scroll	1 📑 🏢
	🔽 Scroll Down	Samples to Scroll	1 🕂 🏢
	Scroll Left	Samples to Scroll	1 📑 🏢
(ABC)	Scroll Right	Samples to Scroll	1 🕂 🏢
	Print-All		
Select Shape	Print-Display		
	Switch Label		
	Font Type Standard Font	Select Switch	
	Display ASCII	Scroll Up	_
	Language	UP	
	Text Color 7	_	
	Switch Color		
	Border Color 7	▼ Blink	None
	Display Color 📃 2	✓ Blink	None
	Pattern None	▼	

Setting		Description			
Part Shape		Displays the shape that you chose for the switch with [Select Shape].			
Sel	ect Shape	Open the [Select Shape] dialog box to choose the switch shape.			
ayout	Scroll Up/ Scroll Down/ Scroll Left/ Scroll Right	Select to place switches to scroll the [Show CSV] Display in each direction.			
Switch Layout	Samples to Scroll	When selecting a switch to place, set how many rows or columns to scroll when pressed. The setting range is from 1 to 1000.			
Š	Print - All	Select to place a switch to print all CSV data.			
	Print - Display	Select to place a switch to print the currently displayed CSV data.			
	Font Type	Choose the label font for the switches. [Standard Font], [Stroke Font] can be selected.			
Switch Label	Display Language	Select a language for the label on the switch: [ASCII], [Japanese], [Chinese (Traditional)], [Chinese (Simplified)], [Korean], [Cyrillic Alphabet] or [Thai].			
vitc	Text Color	Select the font color that will display on the switch labels.			
Ś	Select Switch	Select the switch that you want to type a label for.			
	Label	Enter the text that you want to display on the switch selected in [Select Switch].			
	Border Color	Select a border color for the Switch.			
	Display Color	Set the switch color.			
	Pattern	Select the switch pattern from 9 types.			

Continued

	Setting	Description
	Pattern Color	Select the switch pattern color.
Switch Color	Blink	 Select the blink and blink speed. [Font Color], [Border Color], [Display Color] and [Pattern Color] can be set up with different blink settings. NOTE There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. * "8.5.1 Setting Colors ■ List of Compatible Colors" (page 8-36)
		 Depending on the switch type, [Switch Color] may be enabled. When you select a switch and press the [F2] key you can directly edit the text on the label.

File Manager

The File Manager displays data saved on the CF Card or USB storage device. You can also copy the data between CF Card and USB storage, and select and play movie files stored on the CF Card or FTP Server.

- To display an image (JPEG file) in a CF Card, you should place and set the picture display as well as the file manager. ^{CP™} ■ CF Image Display[™] (page 9-45)
 - The display unit cannot show JPEG files saved on the USB storage device.
 - To play a Movie File stored in the CF Card or the FTP Server, you need to place and set the Movie Player as well as the File Manager.
 - ⁽ Selecting a Movie at Run Time" (page 27-35)

Basic

Basic Switch			
Display Unit			
	A	CSV	a
C Data Transmission	Filing	Show CSV	
Data transmission	r IIIrig	anow Cav	File Manager
Status Address			
Status Address			
Action Mode			
File Operation	-		
Target Data			
OF			
lor.			

Set the 15 Errc	word address to sto	0		
15 Errc	5 12 11	0		
	Set the word address to store the error status.			
Error	Code (Reflected in	the error status)		
0	Completed Successfully	Transfer completed successfully.		
1	Reserved	-		
2	Reserved	-		
3	Reserved	-		
4	No CF Card	No CF Card is inserted or the cover is open.		
5	Read Error	Reading data from CF Card/USB storage failed.		
6	Write Error	Writing data to the CF Card/USB storage device, possibly due to insufficient disk space.		
7	CF Card Error	CF Card is invalid or the media inserted is not a CF Card.		
8	Delete Error	Read-only file, or file delete failed		
9	FTP Connection Error	FTP Server not working properly, or FTP Server does not exist		
10	FTP Login Error	User Name or Password set in the FTP Server not correct		
11	FTP Read Error	Reading file from an FTP server failed		
12	Reserved	-		
13	Reserved	-		
14	USB storage None	USB storage is not available.		
15	USB storage Error	USB storage cannot be accessed or the proper device is not inserted.		
	$ \begin{array}{c} 0\\ 1\\ 2\\ 3\\ 4\\ 5\\ 6\\ 7\\ 8\\ 9\\ 10\\ 11\\ 12\\ 13\\ 14\\ \end{array} $	Error Code (Reflected in 0 Completed Successfully 1 Reserved 2 Reserved 3 Reserved 4 No CF Card 5 Read Error 6 Write Error 7 CF Card Error 8 Delete Error 9 FTP Connection Error 10 FTP Login Error 11 FTP Read Error 12 Reserved 13 Reserved 14 USB storage None 15 USB storage		

Continued

Sotting			Description
Setting			Description
Mode	File Operation	Target Data	 CF Displays folders or files saved in the Saving Data in the CF Card on the screen CFUSB storage You can display both CF card and USB storage at the same time, and copy and move the date between the CF card and USB storage. Use it when you display the CSV data in USB storage on the [CSV Display].
	Movie Selection	Selection Mode	 Single You can select and play only one movie file stored in the CF Card or the FTP server. Multiple You can select and play movie files stored in the CF Card or the FTP server. You can select up to 100 files or folders. Index Numbers will be allocated in order from "0" just like Play List files. Playback will start from the Index Number 0.
		Target Data	 CF You can select data in the CF Card. FTP You can select data in the FTP Server. CF/FTP You can select data in the CF Card or the FTP Server.

Switch

Configure the parameters for the Display switch used to call up the [File Manager] Display from a base screen.

Parts ID SP_0000 📩 Comment	Basic Switch Switch Layout I⊄ Display	
ABC Select Shape	Switch Label Font Type Standard Font Display Language ASCII Text Color 7 UISP	
	Switch Color Border Color Display Color Pattern None I	None 💌 None 💌

Setting		Description	
Part Shape		Displays the shape that you chose for the switch with [Select Shape].	
Select S	hape	Open the [Select Shape] dialog box to choose the switch shape.	
Switch Layout	Display	Designate whether or not to place a switch to display a [File Manager] Display on the base screen.	
	Font Type	Choose the label font for the switches. [Standard Font], [Stroke Font] can be selected.	
Switch Label	Display Language	Select a language for the label on the switch: [ASCII], [Japanese], [Chinese (Traditional)], [Chinese (Simplified)], [Korean], [Cyrillic Alphabet] or [Thai].	
	Text Color	Select the font color that will display on the switch labels.	
	Label	Enter text for the selected switch.	
	Border Color	Select a border color for the Switch.	
	Display Color	Set the switch color.	
	Pattern	Select the switch pattern from 9 types.	
Switch Color	Pattern Color	Select the switch pattern color.	
		Select the blink and blink speed. [Font Color], [Border Color], [Display Color] and [Pattern Color] can be set up with different blink settings.	
	Blink	 NOTE There are cases where you can and cannot set Blink depending on the Display Unit and System Settings' [Color Settings]. ^{CP} "8.5.1 Setting Colors ■ List of Compatible Colors" (page 8-36) 	
• Depending on the switch type, [Switch Color] may be enabled.			

When you select a switch and press the [F2] key you can directly edit the text on the label.

25.11 How to Transfer CSV Data

25.11.1 How to Transfer CSV Data

The Destination Address and other information is not included in created CSV data. Set the condition necessary for transfer (Destination Address, Number of Data Items, etc.) separate from the data.



Condition Example

Collected files to be transferred to the same address are set as a single condition (GROUP). In the file name [ZR****.csv], **** represents the file number portion.

Condition Number	Condition Name	Address	Number of Data Items	File Number
0	Material 1	D100 -	6	0 to 9
1	Temp.	D110 -	3	10 to 19
2	Material 2	D300-	50	20 to 99

This is the start address for the transfer destination (or transfer source.) You can set up either the address for an external device or an internal address.

Designate the range (the start number to the termination number) of the files you want to transfer with the same condition.



When the ZR00000.csv and ZR00010.csv files are transferred to the device/PLC, ZR0000.csv is written depending on Condition Number 0, and ZR00010.csv is written depending on Condition Number 1.



NOTE

- If the number of data items designated in the condition settings differs from that of the CSV Data Recipes, the smaller number of data items is transferred.
- Ensure that the file numbers set in the condition settings ([Start] to [End]) are not repeated in multiple conditions. If file numbers are repeated in several conditions, data are transferred according to the condition with the smaller number.

Condition Number	Condition Name	File Number
0	Product A	0 - 3
1	Product B	2 - 5

The overlapping files ZR00002.CSV and ZR00003.CSV are transferred according to Condition Number 0.

 Without using preset condition settings, you can set the condition (Destination Address, Number of Data Items, etc.) at the time of transfer.
 "25.11.2 Control Word Address For Address Action" (page 25-92)

25.11.2 Control Word Address

This address controls the transfer when automatically transferring CSV data. The address contents are different when you transfer with the [Condition Action] or with the [Address Action].

For Condition Action

Set the number of files and the file numbers to transfer. When bit 0 of the [Control Word Address] turns ON, CSV data from the CF Card/USB storage is written to the device/PLC. When bit 1 turns ON, device/PLC data is saved to the CF Card/USB storage according to the [Condition].

A maximum of 64 files can be transferred simultaneously.



Control

Data transfers depending on the address bit 0 or bit 2 state.



Status

Transfer state and result is reflected in this address.



Error Codes (Reflected in the error status bits)

0	Completed Successfully	Transfer completed successfully.
1	No File Number	When transferring CF/USB to Device/PLC, the transfer destination file does not exist.
2	No Transfer Condition Number	For transfer, the Condition Number that corresponds to the specified File Number (GROUP NO) does not exist.
3	Internal Device Range Error	For a CF/USB to device/PLC transfer where the start address of the transfer is specified to the internal device, data transfer is made to an address outside the specified range of the internal device.
4	No CF Card or USB Storage	The CF Card/USB storage is not inserted in the GP, or the CF Card cover is not closed.
5	Read Error	The read-out from the CF Card/USB storage failed in the CF Card/USB storage to device/PLC data transfer.
6	Write Error	Data writing failed in the device/PLC to CF Card/USB storage data transfer, or there is not enough available space.
7	CF Card Error/USB Storage Error	The CF Card/USB storage device is invalid or the media inserted is not a CF Card/USB storage device.
8	Reserved	-
9	No Retrieve Text	No CSV file matches the retrieve text.
10	Index File Error	The index file format is incorrect.

• Number of Files

Specify the number of CSV files to transfer (from 1 to 64).

If this value is not set, data is not transferred when the [Control Word Address] turns ON. Also, status will not restart.

• File Number 1

Stores the first File Number to transfer.

After that, the desired transfer order is stored by file number.

Automatic Transfer (Condition Action) Timing Chart

When the control address bit 0 (or bit 1) turns ON, the Transferring bit (status bit 0) turns ON. When a data transfer is completed successfully, the Transferring bit turns OFF, and the Transfer Complete Flag (status bit 1) turns ON.

When the data transfer is completed, determine the Transfer Complete Flag via the device/ PLC and turn OFF the Control Address' bit.

Turning OFF the Control Address bit automatically turns OFF bit 1 (transfer complete) in the status address.



If the transfer fails, the Transferring Bit turns OFF, and the error code is set in the error status (status bits 12-15). Before starting the next transfer, clear the Status and Control bits to 0 and turn on the required Control bit.

Bit Control Address		
Transferring Bit (status)		
Error Status (status)	 	
Data Transfer	 Data Transmission	
		Data transfer is interrupted.

For Address Action

The device code and address $code^{*1}$ defined when transferring, also defines the transfer destination (or source) address for each CSV file.

Only one file (1 set of CSV data) can be transferred at a time.

The [Control Word Address] uses 16 consecutive words and designates the data to transfer and the destination address.

• Even when the control address is 32 bit, the address uses 16 words.



After setting the file number, mode, device code, address code, and number of data, when the [Control Word Address] bit 0 turns ON, the designated file number's Recipe (CSV data) is written to the specified address.

Also, when the [Control Word Address] bit 1 turns ON, the Recipe stored in the device/PLC's designated address is saved to the CF Card/USB storage.

Control

Data is transferred depending on the state of this address' 0 and 1 bits.



NOTE

Ensure that all bits in this address are set to "0" when the GP unit is turned on.Do not turn multiple bits ON at the same time.

*1 Each device has a unique Device Code and Address Code. Refer to the "GP-Pro EX Device Manual" for more information.
If you want to specify the GP Internal Device (LS/USR), set the Address Mode to "1".
Then you can set the Device Code as follows:
LS Device: 0x0000
USR Device: 0x0001

Status

Transfer state and result is reflected in this address.



Error Codes (Reflected in the error status bits)

0	Completed Successfully	Transfer completed successfully.	
1	No File Number	When transferring CF/USB to Device/PLC, the transfer destination file does not exist.	
2	Reserved	-	
3	Internal Device Range Error	For a CF/USB to device/PLC transfer where the start address of the transfer is specified to the internal device, data transfer is made to an address outside the specified range of the internal device.	
4	No CF Card or USB Storage	The CF Card/USB storage is not inserted in the GP, or the CF Card cover is not closed.	
5	Read Error	The read-out from the CF Card/USB storage failed in the CF Card/USB storage to device/PLC data transfer.	
6	Write Error	Data writing failed in the device/PLC to CF Card/USB storage data transfer, or there is not enough available space.	
7	CF Card Error/USB	The CF Card/USB storage device is invalid or the media	
	Storage Error	inserted is not a CF Card/USB storage device.	
8	Delete Error	File delete failed, or read-only file.	
9	Reserved	-	
10	Reserved	-	

• File Number

Specify the file number to be transferred.

• Mode

Set the Recipe data format to allow negative numbers.



Address Mode



Device code and address code Specify the device you want to access with the Device Code. You can also specify the destination (or source) address with the Address Code. Device and Address codes differ depending on the device. Refer to the "GP Pro FX

Device and Address codes differ depending on the device. Refer to the "GP-Pro EX Device/PLC Manual" for more information. To specify the GP internal device in Address Mode, use device code 0x0000 for the LS device, and device code 0x0001 for the USR device.

Number of Data Items

Designate the number of data items in the CSV Data Recipe. The maximum number of data items is 10,000 for 16 bit and 5,000 for 32 bit. If the number of data items exceeds this limit, the transfer operation will not work.

Automatic Transfer (Address Action) Timing Chart

When the data transfer is completed, status bit 1 (Transfer Complete Flag) turns ON. Turn OFF the trigger bit after the Transfer Complete Flag is displayed via the device/PLC. Turning OFF the trigger bit automatically turns OFF Transfer Complete Flag on the status address.



Address Action Transfer Example

Writing from the CF Card/USB to Device/PLC

For example, transferring "ZR00001.csv" (Number of Data Items: 6, Data length: Control Word Address: D50

D50	Control	
D51	Status	
D52	File Number	
D53	Mode	
D54	Address Mode	
D55	Device Code	
D56	Address Code	
D57	(2 words)	
D58	Number of Data Items	
D59		
	Reserved Area	
	(7 words)	
D65		

- 1 Write the transfer file number "1" to D52.
- 2 Write "0" (16 Bit, No Sign) to D53.
- **3** Write "0" to D54.

• When the transfer destination is the internal device, write "1".
• For memory link type, set "0".

- 4 Write the transfer destination device "0x0000" (D device) to D55.
- 5 Designate the transfer destination address in D56/D57. Write "100" to D56 and "0" to D57.
- 6 Write "6" to D58.
- 7 Turn ON D50 bit 0. CSV data is written to addresses D100 to D105.
- **8** When the data transfer is completed, turn OFF bit 0 of D51 (the [Transferring] bit). Turn ON the [Transfer Complete Flag] (bit 1).

Reading from the Device/PLCCF/USB

For example, transfer six data items (Data Length: 16 Bit, No Sign) from the device/PLC, D100 to D105, to the CF Card and create the file ZR00002.csv.

- 1 Write the file number "2" to be created by transfer to D52.
- **2** Write "0" (16 Bit, No Sign) to D53.
- **3** Write "0" to D54.
- 4 Write the transfer source device "0x0000" (D device) to D55.
- 5 Designate the transfer source address in D56/D57. Write "100" to D56 and "0" to D57.
- 6 Write "6" to D58.
- 7 Turn ON D50 bit 1. The data from D100 to D105 are read and the file name "ZR00002.csv" is created in the CF Card [File] folder.

When the data transfer is completed, turn OFF bit 0 of D51(the [Transferring] bit). Turn ON the [Transfer Complete Flag] (bit 1).

• When transferring from device/PLC to CF/USB, the CSV Data date is set in the two-digit format.

◆Delete File

NOTE

For example, Delete file name "ZR00002.csv" from the CF Card.

- 1 Write the file number "2" to delete to D52.
- 2 Turn ON D50 bit 15 (Deletion bit).

When the file deletion is completed, D51 bit 1 (Transfer Complete Flag) turns ON.

25.11.3 About the Condition Name Search Feature

When automatically transferring from CF/USB -> device/PLC, by designating the condition name of the file you want to transfer, you can search for a matching CSV file within the CF Card/USB storage [FILE] folder and transfer that data to the device/PLC.

In the following picture, the CSV files that match the product number (condition name) read from the barcode reader are transferred to the device/PLC.



NOTE

• The search only detects files whose condition name is an exact match for the search string. Spaces indicate different file names and can cause errors.

The designated [Search Word Address] uses 16 words, and the condition name to be searched can be up to 32 characters. After storing the search condition name, turn ON bit 2 of the [Control Word Address]. The search and transfer to the device/PLC begins. If there are multiple matching files, the CSV data are transferred in order of file number.

 Control Word Address when Using the Condition Name Search Feature" (page 25-99)
 Condition Name Constant Operation Mathematical (page 25-404)

Condition Name Search Storage Methods" (page 25-101)

If an index file (ZRINDEX.CSV) exists in the CF Card's [FILE] folder, the search scans the contents of the index file.

If there is no index file and the [File] folder contains a large number of files, referencing and searching the condition names of all CSV files may take a long time. For example, if approximately 1,000 CSV files are searched, the search operation takes approximately one minute.

• Even if the target file exists in the CF Card [FILE] folder, files whose condition name is not reflected in the index file cannot be detected. Either update or delete the index file and then transfer the files.

What is an Index File?

In GP-Pro EX, create CSV data and click [Search File]. In the [FILE] folder, an index file (ZRINDEX.csv) will be created.

When using the Condition Name Search feature, this file is used to speed up the search. The File Number and Condition Name for the CSV data recipes in GP-Pro EX are written to this file.

The index file has the following format:



In GP-Pro EX, after you run CSV file operations such as adding, editing, or deleting from the [Recipe] [Transfer CSV Data (CSV File List)] command, click [Search File] to update the index file.

If a CSV file has been created in Excel or by a device/PLC and transferred to the CF card or USB storage, the index file will not reflect information from those files. Either open the index file and input the information directly in the file, or add/edit the index file in GP-Pro EX.

NOTE	 When editing the index file, do not create any index file errors.Condition Name Search feature will fail. In such cases, create a new index file or delete the existing index file before resuming the transfer operation. The index file can be deleted by using a Special Data Display [File Manager]. (1) A file number is missing. (2) The file number is not within the range of 0 to 65535. (3) The index file is not in CSV file format.
	 The index file condition names and file numbers are created by referencing all the saved files in the [File] folder. It is not created based on GP-Pro EX condition settings. An index file can be created while offline. Refer to Maintenance Troubleshooting Guide for Offline Screen. When creating an index file while offline, the file will be overwritten if there is already an index file in the designated external storage.

Control Word Address when Using the Condition Name Search Feature

After storing the Condition Name to search, turn the [Control Word Address] transfer bit (bit 2) from OFF to ON to: search for CSV files within the CF Card/USB storage and transfer all CSV files that match the search condition name.



Control

When bit 2 turns ON, search for the file with the condition name that matches the text string designated in [Search Word Address], and write the matching CSV data to the PLC.



Status

Transfer state and result is reflected in this address.



Error Codes (Reflected in the error status bits)

0	Completed	Transfer completed successfully.
1	Successfully	Without the sector of the Control of the terms for
1	No File Number	When transferring CF/USB to Device/PLC, the transfer destination file does not exist.
2	No Transfer	For transfer, the Condition Number that corresponds to the
	Condition Number	specified File Number (GROUP NO) does not exist.
3	Internal Device	For a CF/USB to device/PLC transfer where the start address
	Range Error	of the transfer is specified to the internal device, data
		transfer is made to an address outside the specified range of
		the internal device.
4	No CF Card or USB	The CF Card/USB storage is not inserted in the GP, or the
	Storage	CF Card cover is not closed.
5	Read Error	The read-out from the CF Card/USB storage failed in the CF
		Card/USB storage to device/PLC data transfer.
6	Write Error	Data writing failed in the device/PLC to CF Card/USB
		storage data transfer, or there is not enough available space.
7	CF Card Error/USB	The CF Card/USB storage device is invalid or the media
	Storage Error	inserted is not a CF Card/USB storage device.
8	Reserved	-
9	No Retrieve Text	No CSV file matches the retrieve text.
10	Index File Error	The index file's CSV format is incorrect.

Condition Name Search Transfer Timing Chart

When the control address' bit 2 turns ON, the [Transferring] bit (status bit 0) turns ON. When a data transfer is completed successfully, the Transferring bit turns OFF, and the Transfer Complete Flag (status bit 1) turns ON.

When the data transfer is completed, determine the Transfer Complete Flag via the device/ PLC and turn OFF the Control Address' bit. When the trigger is OFF, the [Transfer Completion] bit turns OFF.



If the transfer fails, the Transferring Bit turns OFF, and the error code is set in the error status (status bits 12-15). Before starting the next transfer, clear the Status and Control bits to 0 and turn on the required Control bit.



• The period during which the Transferring Status Bit is ON includes the time required for the search of the CSV files. Therefore, do not access the [FILE] folder in the CF Card/USB storage while the Transferring Bit is on.

Condition Name Search Storage Methods

In the lower 16 words of the designated [Search Word Address], you can store the condition name according to the Text Data Mode. This can be set to either a device/PLC address or GP internal device address.

If the specified name is less than 32 characters, write 0 (NULL="0(h)") or a blank space in the address following the last character. Characters before the address containing 0 (NULL="00(h)") are considered as the condition name for the search.

Condition Name Search can be performed only for Data Modes 1, 2, 4 or 5. The following are examples of the Text Data Modes.

For example, searching for Condition Name "TYPE-A0001".

• String Data Mode 1



• String Data Mode 2



• String Data Mode 4



• String Data Mode 5



- You can use a space in the condition name to search, but it cannot be in the last position. Spaces between the last character and 0 are replaced with 0 in the matching operation.
 - If the [Search Word Address]'s top position is 0, the search looks for a file without a condition name.

25.11.4 About Automatic Numbering

When automatically transferring from the device/PLC to the CF Card or USB storage device, you can automatically allocate file numbers to create new files. To set up this function, open the [CSV Data Transfer Condition] dialog box and click the [Extended] tab. The automatic numbering action is as follows:

- The new file name is created by adding +1 to the file number with the most recent time stamp among existing files on a CF card/USB storage.
- If no free space is left, the file with the oldest time stamp is deleted and a new file is created by adding +1 to the last saved file number.





If files numbered from "ZR00000.CSV" to "ZR00002.CSV" exist, "ZR00000.CSV" is deleted to create "ZR00003.CSV".

• When the file numbers saved to the CF Card/USB storage device are not sequential, the new file name is created by adding +1 to the file number with the most recent time stamp among existing files.





When the ZR00002.CSV file has not been saved and the ZR00003.CSV file is still new, the application generates ZR00004.CSV.

NOTE

• If the file numbers do not conform to time stamps in automatic numbering mode (when files are overwritten by manual transfer), a new file is created by increasing the most recent File Number by +1.

ZR00000.CSV	10:00
ZR00001.CSV	12:00
ZR00002.CSV	11:00
ZR00003.CSV	9:00

	ZR00000.CSV	10:00
	ZR00001.CSV	12:00
	ZR00002.CSV	13:00
, 	ZR00003.CSV	9:00

When files ZR00000.CSV to ZR00003.CSV already exist, ZR00002.CSV becomes overwritten with a new file.

• When using automatic numbering, do not use manual transfer (Device CF/ USB) and allocate file numbers. These files will be overwritten. Regardless of the timestamp of a manual transfer, files are overwritten, in order, from the number of the last automatically numbered file plus one. If the file number reaches the [End], data will not be transferred even if the [Control Word Address] turns ON. To continue transferring data, use the [Loop] feature or specify the [Resume Bit Address]. • Using the Loop function

When you enable the [Loop] feature, after the [End] is reached, data is overwritten starting from the [Start] and the transfer continues.

For example, when the Condition are: [Start] = 0, [End] = 4



• When using a Resume Bit Address

When the [End] is reached and the designated [Resume Bit Address] turns ON, then the next time the [Control Word Address] turns ON.The [Start] file gets overwritten and the other files after that are overwritten and transferred.

Automatic Numbering Timing Chart

When you create files from [Start] to [End], the [Full Bit Address] turns ON and automatic transfer ends.

To run automatic transfer again, turn ON the [Resume Bit Address], then turn ON bit 1 of the [Control Word Address]. Files are overwritten and created in order starting from the [Start]. When the [Resume Bit Address] turns ON, the [Full Bit Address] is turned OFF. Check that the [Full Bit Address] is turned OFF and turn OFF the [Resume Bit Address].



NOTE • Transfer may not work when files already exist up to the end number in the CF Card or USB storage. When the GP is turned ON, right after turning ON bit 1 in the [Control Word Address], the [Full Bit Address] turns ON. However, if the [Resume Bit Address] is ON, when you turn ON bit 1 in the [Control Word Address], files are overwritten beginning at the start number.Before you run the Transfer operation, you should check the file number stored on the CF Card or USB storage, and also check the state of the [Resume Bit Address].

25.12 Mechanism of Filing Data Transfer

25.12.1 Filing Data Structure

Recipe data is managed in folder units.

One folder can hold a maximum of 2048 files.

One file can handle a maximum of 1650 blocks (recipes). Data transfer is carried out in blocks. Also, the maximum number of data items in 1 file is 10000 or 5000 when the data is 32 bit.



NOTE

- The number of files, blocks, and data that can be set changes depending on the ratio of each one.
 - You can also register files in multiple folders. Up to 8999 folders can be registered, but only one folder can be stored in backup SRAM.



Transfer Preparation when using Multiple Folders

About Backup SRAM

This memory will save data even when the GP unit is OFF.

The backup SRAM user area is used to back up filing data, Alarm History data, Sampling data, and the internal device (User Area).

The capacity of backup SRAM that can be used by filing data depends on the model of GP and how much capacity is being used by other data.



The backup SRAM user area has the following usage priorities:

- (1) Operation Log data
- (2) Alarm History data
- (3) Sampling Data
- (4) User Area Part backup data
- (5) Filing Data
- Data in backup SRAM is erased when: Screen transfer occurs The user area is initialized (Offline) Backup SRAM is initialized (Offline)
 - Data stored in backup SRAM can be saved to a CF Card/USB storage device. To set this option, from the System Settings, select [Display Unit], select the [Action] tab, then select [Data Storage].

 ^{CP} Operation[®] (page 5-151)

Filing Data Capacity

The maximum storage capacity of filing data per file is the maximum capacity of the backup SRAM user area. Folder capacity is calculated in the following way, depending on the number of files, blocks, data, and the bit length.

Calculation

• Usage capacity per file (in bytes)

 $118 + \{(68 + 2^{*1} \text{ x Number of Data Items}) \text{ x Number of Blocks}\}$

- *1 2 bytes when the data length is 16 bit, 4 bytes when the data length is 32 bit.
- Usage capacity per folder (in bytes)

4 + the sum of each file's volume

Calculation Example

Items	Description
Blocks	5
Number of Data Items	1000
Data format (bit length)	16 Bit

For example, folder capacity with only 1 file

[Calculation result]

 $4 + [118 + {(68 + 2 x 1,000) x 5}] = 10,462$ bytes (around 10 KB)

25.12.2 Transferring Item Name and Block Number

In the [Edit Filing Data] > [Option], you can configure settings to transfer data with the item name and block number attached to it.

When transferring both the item name and block number to the device/PLC along with the data, it is stored with the following structure.

💣 Edit Filing Data		X	1
Storage Start Address [PL Display Format De	redient .C1JD00126 Y sc Y Sign Bit Y		Device/PLC D110 1 Block No. D111 Item Name
Block 0 ItemName Block0 [PLC1]D00126 350 [PLC1]D00127 5 [PLC1]D00128 7 [PLC1]D00129 12 [PLC1]D00120 245 [PLC1]D00131 12	Block 1 Block Block 1 Block 400 200 8 4 8 3 16 10 310 120 40 0	Options	D126 D127 D128 D129 D129 D130 D131 D132 40 D131 D132 D132 D130 D132 D130 D132 D130 D132 D130 D16 D132 D16 D17 D128 D127 D128 D130 D130 D130 D132 D132 D132 D132 D132 D132 D132 D132

For example, [Storage Start Address] is a 16 bit address, data is 16 bit

- The item name's text is stored according to the Text Data Mode settings.^{*1}
 - Storage of the item name and data depends on the designated [Storage Start Address] and [Bit Length].
 - The block number is not transferred during a device/PLC -> SRAM transfer. The same applies when transferring via the internal device (Device/PLC -> Internal Device -> SRAM).
 - When using manual transfer via the internal device, the item name will be sent between the SRAM and the internal device regardless of settings in the [Preferences] dialog box.

For example, when only [Send Block Number] is designated





IMPORTANT

- When the Item Name is less than 32 characters, spaces are automatically appended.
- Even when the [Display Format] is set to [BCD], the Block Number are stored in the device/PLC with binary data.
- *1 Text Data Mode settings are configured in the System Settings [Device/PLC].
Data Structure when Transferring both Block Number and Item Name

• When [Storage Start Address] is a 16 bit address (n = Number of Data Items)



• When [Storage Start Address] is a 32 bit address (n = Number of Data Items)



25.12.3 Manual Transfer Via the Internal Device

When a Special Data Display [Filing] is set with [Via Internal Device], you can use a Switch Lamp Part [Special Switch] and point to [File Item Switch] to transfer [SRAM -> Internal Device], [Internal Device], [Device -> Internal Device], and [Internal Device -> SRAM].



NOTE

• A Switch to operate the transfer to and from the internal device can only be created with a Switch Lamp [Special Switch].

For example, when transferring from SRAM to Internal Device (Start Address: LS20) Device/PLC

(Data length: 16 Bit)



Data stored in the internal device can display as required on the GP screen in a Data Display [Numeric Display]. Use this when you want to want to make small adjustments to the data on the GP screen before transferring it to the device/PLC.



Choose the item name with the Filing Display and transfer from SRAM \rightarrow Internal Device.



Internal device data appears in the Data Display. Touch the Data Display and...



A pop-up keypad appears. Edit data and press ENT key.





Transfer from internal device \rightarrow PLC

Structure of Filing Data Stored in the Internal Device

When transferring data from backup SRAM the internal device, the 16 consecutive words after the designated [Storage Start Address] store the item names, and data are stored after that.

The item name will be stored according to the Text Data Mode settings.^{*1}

For example, when data is 16 bit:



NOTE

• When data is 32 bit, the used data portion is Number of Data Items x two words.

*1 Text Data Mode settings are configured in the System Settings [Device/PLC].

When transferring data from the internal device to the device/PLC, only data stored in the internal device are written to designated addresses in the device/PLC.



25.13 Restrictions

25.13.1 Restrictions on Transferring CSV Data

- The maximum number of data that can be set in one file (ZR*****.csv) is 10,000 (or 5,000 when the data is 32 bit).
- If the number of data is large, transfer may take some time. The time from when transfer starts to when transfer is complete can vary from several seconds to several minutes.
- While a transfer is occurring, the display of Parts may not update properly or may become slow. Screen changes and other operations may also become slow.
- If a screen change occurs during transfer, in order to read the screen information, the transfer may take some time.
- Wait until a transfer completes before initiating another one. If a transfer is started before the previous one ends, such as when an automatic transfer and manual transfer occur at the same time, the second transfer operation may not be accepted.
- Only the selected CF Card or USB storage device will operate.
- If multiple files are stored in the CF Card/USB storage [File] folder, transferring to the device from CF Card/USB storage may take up to several minutes.
- Do not call up screens that use the CF Card/USB storage when the CF Card/USB storage is not installed on the GP. It may not work properly.
- When a CF Card/USB storage error occurs, temporary files may remain on the CF Card/ USB storage device.
- When overwriting, the required available space on the CF Card or USB Storage is at least double the size of the actual data. If there is more data than available space, a write error occurs during transfer. To free up space, you can move out data that is not needed immediately between the CF Card and USB Storage. If the data exceeds the free space, a write error occurs when it is transferred.

^(C) "A.5 Transferring Data Between a CF Card and a USB Memory Device" (page A-83)

- When transferring data from device/PLC to CF/USB, the [File] folder is created if it does not already exist. If the CF Card/USB storage is not reset or the folder cannot be created, a CF Card/USB storage error occurs.
- When you save the existing CSV data in the CF Card/USB Storage, if there is data entered in the third row or later in the CSV data, it will be deleted upon saving.
- The number of times that data can be written on a CF Card is limited. (Approximately 100000 times for rewriting 500 KB.)
- When saving data in a CF Card, you cannot use a file name or folder name with two-byte characters. The file name/folder name should be 8 single-byte characters or less.
- To format the CF Card/USB storage on your PC, select FAT or FAT32. If you use NTFS for formatting, GP does not recognize the CF Card/USB storage.

- Do not connect more than one USB storage device. If you do so, the USB devices may not be recognized.
- When using Float, up to 17 digits or 16 decimal places can be read, but an error may occur after the seventh digit due to floating point limitations.
- When transferring from the CF card or USB storage to the device/PLC, tabs and singlebyte space characters are skipped when read. Furthermore, when there are periods or commas in comments, there are instances when the data text cannot be read properly. When there are two or more commas in a single row, data after the second comma is not read.

CF Card Cautions for Use

- When ejecting a CF Card, make sure that the CF Card access LED lamp turns OFF. Otherwise, the data on the CF Card may be damaged.
- When accessing a CF Card, be sure not to power OFF or reset the GP, or eject the CF Card. Create an application screen on which the CF Card cannot be accessed, and on that application screen, you may power OFF or reset the GP, open and close the CF Card cover, and eject the CF Card.
- When inserting a CF Card, check the front and back sides and the connector position of the card. If the CF Card is inserted the wrong way, the data, the CF Card, or the GP may be damaged.
- Use a CF Card manufactured by Digital Electronics Corporation. If a CF Card manufactured by another company is used, the contents of the CF Card may be damaged.
- Please make sure to back up all CF Card data.
- Please refrain from doing the following, as it can result in damage to data and equipment:
 - •Bending the CF Card
 - •Dropping the CF Card
 - •Spilling water on the card
 - •Touching the CF Card's connectors directly
 - •Disassembling or modifying the CF Card

USB Storage Cautions for Use

- While accessing the USB storage device, do not reset the GP insert or remove the USB storage device. The data on the storage device may be corrupted.
 - To remove the USB storage device safely, design the system so that the device is removed after turning ON the System Variable #H_Control_USBDetachTrigger and confirming that the #H_Status_USBUsing is OFF.
 - ⁽ A.6.2 HMI system variables (#H system variables) Bit type" (page A-108)
- Please make sure to back up all data on the USB storage device.

Restrictions for Manual Transfer

- First set the Condition on [Recipe] [Transfer CSV Data (Condition)], then place the Special Data Display [Data Transmission] on the screen.
- Only one Special Data Display [Data Transmission] can be placed per screen.
- Up to 32 Special Data Display [Data Transmission] can be placed per project.
- When selecting transfer files by touch, multiple files can only be selected from the area displayed in a Special Data Display [Data Transmission]. (The maximum number of display rows is 50.) If the displayed page changes with the scroll switch, the selection cancels.
- If an error occurs while transferring multiple files, transfer stops at that file. Subsequent files are not transferred.

- When transferring data from the device/PLC to the CF/USB, the data is saved in the file set in the Special Data Display [Data Transmission]. The Condition Name (Group Name) is overwritten by the Condition Name set in the Common Settings Condition area.
- If the number of data designated in the condition settings differs from that in the file, the smaller number of data are transferred.
- Ensure that the file numbers set in the condition settings ([Start] to [End]) are not repeated in multiple conditions. If file numbers are repeated in several conditions, data are transferred according to the condition with the smaller number.

Restrictions on Automatic Transfer (Conditional Action)

- A maximum of 64 files can be transferred at one time.
- If an error occurs while transferring multiple files, transfer stops at that file. Subsequent files are not transferred. Transfer occurs in order starting from the top file number storage address.
- If the number of data designated in the condition settings differs from that in the file, the smaller number of data are transferred.
- Ensure that the file numbers set in the condition settings ([Start] to [End]) are not repeated in multiple conditions. If file numbers are repeated in several conditions, data are transferred according to the condition with the smaller number.
- If the number of files is not set, data are transferred even when the [Control Word Address] turns ON. Also, status will not restart.
- When transferring data from device/PLC to CF/USB, the [File] folder is created if it does not already exist. If the CF Card/USB storage is not reset or the folder cannot be created, a CF Card/USB storage error occurs.

Restrictions on Automatic Transfer (Address Action)

- One CSV Data Recipe can be transferred at a time.
- When transferring CSV Data Recipes from CF/USB to device/PLC using a memory link connection, set the [Address Mode] to "0".
- If the number of data exceeds the set range (10,000 when the data length is 16 bit, 5,000 when it's 32 bit), any excess values are not transferred.
- Ensure that the device code/address code is set correctly. If the device address is out of range or refers to a non-existent device, a communication error occurs and the screen freezes.

If a communication error occurs while transferring from device/PLC τ o CF/USB, correct the device code/address code. Turn ON bit 1 of the [Control Word Address] again. If the error occurs while transferring from CF Card /USB to device/PLC, turn the power to the GP OFF then ON.

• When transferring data from device/PLC to CF/USB, the [File] folder is created if it does not already exist. If the CF Card/USB storage is not reset or the folder cannot be created, a CF Card/USB storage error occurs.

25.13.2 Restrictions on Displaying/Editing/Printing CSV Data

Restrictions on Displaying

- Only one Special Data Display [Show CSV] can be placed per screen.
- Only one Special Data Display [File Manager] can be placed per Base Screen. It cannot be placed on a Window Screen.
- When you place a Special Data Display [Show CSV] on a Window Screen, you cannot edit the data. The editing screen cannot be triggered.
- You cannot set a Special Data Display [Show CSV] at the same time as a Sampling Data Display or Data Display (a Numeric Display with [Allow Input] set or a Text Display).
- The Special Data Display [File Manager] cannot be scaled up or down.
- When placing a Special Data Display [File Manager], specify the X coordinate in 4-dot increments. If you place it in a different position, it will not be displayed in the exact position it was on the screen in GP-Pro EX because the GP corrects the display position.
- You can display the Special Data Display [File Manager] part using a Special or Local Window. If the maximum number of windows are already displayed, the File Manager does not appear. Close other windows to display the [File Manager] display part.
 * "12.8 Restrictions for Windows" (page 12-29)
- To access CSV data in the USB storage device, use the Special Data Display File Manager part.
- When a text table changes, the Special Data Display File Manager is closed.
- If more than one display switch for a Special Data Display [File Manager], touching another display switch while a File Manager is already displayed closes the [File Manager] window that is currently displayed.
- Files currently displayed on a Special Data Display Show CSV cannot be deleted with a Special Data Display -File Manager.
- When updating by transfer from the device/PLC to CF/USB, the displayed CSV file data is updated and rewritten.
- If the cover of the CF Card slot is open or the USB storage device is removed while CSV file data is displayed, the display is cleared.
- If the screen changes while CSV data is displayed, the display is cleared.
- There are two valid data formats for CSV data displayed in a Special Data Display [Show CSV]: data delimited by double quotation marks [""], and data separated by commas [,].

For example, CSV format (Sampling data)

```
"", "Date", "Time", "Data 0", "Data 1"
"Number1", "01/12/05", "09:00:00",
"123.4", "780"
"Number2", "01/12/05", "10:00:00",
"213.5", "235"
```

,Date,Time,Data0,Data1 Number 1, 01/12/05, 09:00:00, 123.4, 780 Number 2, 01/12/05, 10:00:00, 213.5, 235

Restrictions for Editing

- The editing screen for a Special Data Display [Show CSV] displays via a Special or Local Window. If the maximum number of windows are already displayed, the editing screen cannot be activated. Close another window before editing the data.
 ** "12.8 Restrictions for Windows" (page 12-29)
- You can edit up to 56 characters in a Special Data Display [CSV Display]. This limit depends on the model and orientation.
- If you try to save data to the CF Card or USB storage device during an edit operation, a write error will occur. Data cannot be saved while editing.
- If data are changed during editing, a CF write error occurs and is stored in the [Status Address]. The displayed data are not updated.
- When a text table changes, the editing screen will be automatically closed.
- Even when the [Interlock Address] state matches the [Touch Enable Condition] during editing, editing can be performed. However, if editing is attempted again, the screen will not enter Edit mode because the Interlock feature is enabled.
- Numeric values displayed on a Special Data Display [Show CSV] are displayed as text. Therefore, the inputs are edited regardless of properties such as the number of display digits, data length, and data type.
- While the edited data is being output to a CSV file, printing and editing modes are disabled. Also, the system cannot be moved to off-line mode.
- Regardless of the Show Column settings, the column portion cannot be edited.
- When editing data, a temporary file is created on the CF Card/USB storage device. As a result, free space equivalent to the size of the file being edited must be available. You cannot edit the file if this capacity is not available.

When editing data, the internal processing updates the file in the following way: For example, when editing "ZR0001.CSV"

- (1) After pressing the [ENT] key, a temporary file (a file that reflects the editing results), "_CSV\$\$_0.TMP" is created.
- (2) The original file name is changed from "ZR00001.CSV" to "_CSV\$\$_1.TMP"
- (3) "_CSV\$\$_0.TMP" is changed to "ZR00001.CSV"
- (4) "CSV 1.TMP" is deleted.

If the power turns OFF during editing or if editing fails, temporary files may remain on the CF Card/USB storage.

• When a Special Data Display [Show CSV] is rotated by 90 or 180 degrees, the editing screen characters are not displayed properly. To place a rotated [Show CSV], set rotation to 0 or 270 degrees.

Restrictions for Printing

- The horizontal lines are not printed.
- Any portion that exceeds an A4 width is not printed. The number of characters that can be printed on one line depends on the printer.
- Up to 160 characters can be printed in a single line. Any text exceeding 160 characters is cut off.
- Regardless of the Show Column settings, the column portion will not be printed.
- When printing only the displayed portion, if the data in the right most cell extends beyond the screen and is cut off on the Show CSV Display, that portion is also cut off on the printout.
- While printing, the data cannot be edited or printed. Also, the system cannot be switched to off-line mode.

25.13.3 Restrictions on Transferring Filing Data

- Up to 8999 folders can be registered. However, only one folder can be stored in backup SRAM.
- The size of one folder can be up to the same size as the total capacity of the backup SRAM when only recipes are stored. Even when filing data is stored on a CF Card/USB storage device, regardless of the CF Card/USB storage memory capacity, one folder must have a capacity equal to the backup SRAM's maximum capacity.
- Up to 2048 files can be set in one folder.
- Up to 1650 blocks can be saved in one file. (The maximum number changes depending on the Number of Files and Number of Data Items.)
- The maximum amount of data in one block is 10000 for 16-bit data, or 5000 for 32-bit data. The maximum limit depends on the number of files and number of blocks.
- The more data transferred to the device/PLC, the more time it takes to complete the write operation. The time from when transfer starts to when transfer is complete can vary from several seconds to several minutes.
- While writing to a device/PLC, the display of Parts may not update properly or may become slow. Screen changes and other operations may also become slow.
- If a screen change occurs during transfer, in order to read the screen information, it may take some time to write to the device/PLC.
- Wait until a transfer completes before initiating another one. If a transfer is started before the previous one ends, such as when an automatic transfer and manual transfer occur at the same time, the second transfer operation may not be accepted.
- Data in backup SRAM is erased when:
 - On Screen Transfer
 - Memory is reset (Offline)
 - Backup SRAM is initialized (Offline)
- When placing multiple Special Data Displays [Filing] on one screen, do not use the same [ID Number] for multiple Displays.
- You cannot move the generated Recipe data to a different project for editing.
- Recipe data generated in the CF Card or USB Storage Designation Folder cannot be used in other projects.